

Dartmouth College

## Dartmouth Digital Commons

---

Computer Science Technical Reports

Computer Science

---

12-1-2008

### Digital Image Ballistics from JPEG Quantization: A Followup Study

Hany Farid

*Dartmouth College*

Follow this and additional works at: [https://digitalcommons.dartmouth.edu/cs\\_tr](https://digitalcommons.dartmouth.edu/cs_tr)



Part of the [Computer Sciences Commons](#)

---

#### Dartmouth Digital Commons Citation

Farid, Hany, "Digital Image Ballistics from JPEG Quantization: A Followup Study" (2008). Computer Science Technical Report TR2008-638. [https://digitalcommons.dartmouth.edu/cs\\_tr/320](https://digitalcommons.dartmouth.edu/cs_tr/320)

This Technical Report is brought to you for free and open access by the Computer Science at Dartmouth Digital Commons. It has been accepted for inclusion in Computer Science Technical Reports by an authorized administrator of Dartmouth Digital Commons. For more information, please contact [dartmouthdigitalcommons@groups.dartmouth.edu](mailto:dartmouthdigitalcommons@groups.dartmouth.edu).

# Digital Image Ballistics from JPEG Quantization: A Followup Study

Hany Farid  
Department of Computer Science  
Dartmouth College  
Hanover NH 03755

## Abstract

The lossy JPEG compression scheme employs a quantization table that controls the amount of compression achieved. Because different cameras typically employ different tables, a comparison of an image’s quantization scheme to a database of known cameras affords a simple technique for confirming or denying an image’s source. This report describes the analysis of quantization tables extracted from 1,000,000 images downloaded from *Flickr.com*.

## 1 Introduction

Since the JPEG image format has emerged as a virtual standard, most cameras encode images in this format. This lossy compression scheme allows camera manufacturers to balance the amount of compression and the quality of their images. This tradeoff is embodied in the JPEG quantization table. In earlier work [1], we showed that the quantization table is fairly distinct across various cameras, and can therefore be used to confirm or deny the source of an image (see also [2]). This initial study examined one image taken from one of 204 cameras, but suffered from not considering the different quantization tables that are employed with varying camera quality and resolution settings. In this report, we expand on our earlier work by considering a much larger and more diverse collection of images.

## 2 Methods


Using the *Flickr* API, 1,000,000 images were downloaded from *Flickr.com*, a popular photo-sharing website. Since we are interested in the JPEG quantization table employed by different cameras, it was necessary to eliminate any images that had been edited or altered by any photo-editing software. To this end, only images tagged as “original” by *Flickr* were downloaded. Images were then eliminated if they were not 3-channel color images, and further eliminated if they had incomplete metadata, inconsistent “modification” and “original” dates, or a “software” metadata tag suggesting that the image had been edited by a photo-editing software. This filtering eliminated 557,045 images, leaving 442,955 images.

The camera make, model, resolution, and JPEG quantization table were extracted from each of the 442,955 images’ metadata. In order to further eliminate possible edited or altered images, only those entries with five or more images having the same paired make, model, resolution, and quantization table were retained. This filtering eliminated 105,329 images, leaving 337,626 images for the final analysis.

The remaining 337,626 images spanned 10,153 different distinct pairings of camera make, model, resolution and quantization table (accounting for 48 different camera manufacturers, and 859 different camera models). It is from these 10,153 entries that the distinctness of the paired resolution and quantization table was analyzed. Both the resolution and quantization table were combined in order to provide a more refined criteria for narrowing the search criteria to identify the source camera.

## 3 Results

The 10,153 entries described in the previous section fall into equivalence classes of size 1 to 178, where each class has identical resolution and JPEG quantization table. The average class size is 20.13, with a standard deviation of 35.7 (a class of size 1 means that the paired values are unique). The median class size is 5. Of the 10,153 entries, 2,704 entries (26.6%) have a unique paired resolution and quantization table, and 37.2% have at most two matches, and 44.1% have at most three matches.



**Figure 1:** The distribution of equivalence class sizes for paired resolution and JPEG quantization (a class size of 1 denotes a unique pairing).

Shown in Figure 1 is the distribution of the size of these equivalence classes, and shown in Appendix A are the cameras belonging to the same equivalence class. In the majority of cases, it is cameras from the same manufacturer that share the same quantization table, although in several situations there is a significant amount of overlap between cameras of different manufacturers.

If we ignore resolution and partition only on the quantization tables, then the 10,153 entries fall into equivalence classes of size 1 to 899, where each class has an identical quantization table. The average class size is 273.6, with a standard deviation of 276.1. The median class size is 254, and 517 (5.1%) have a unique quantization table, and 8.3% have at most two matches, and 10.4% entries have at most three matches.

## 4 Discussion

While the JPEG quantization table is clearly not unique, it (paired with the image resolution) is reasonably effective at narrowing the source of an image to a single camera make and model or to a small set of possible cameras.

## Acknowledgments

This work was supported by a gift from Adobe Systems, Inc., a gift from Microsoft, Inc., a grant from the National Science Foundation (CNS-0708209),

and by the Institute for Security Technology Studies at Dartmouth College under grants from the Bureau of Justice Assistance (2005-DD-BX-1091) and the U.S. Department of Homeland Security (2006-CS-001-000001). Points of view or opinions in this document are those of the author and do not represent the official position or policies of the U.S. Department of Justice, the U.S. Department of Homeland Security, or any other sponsor.

## References

- [1] H. Farid. Digital image ballistics from JPEG quantization. Technical Report TR2006-583, Department of Computer Science, Dartmouth College, 2006.
- [2] J.D. Kornblum. Using JPEG quantization tables to identify imagery processed by software. *Digital Investigation*, 5:S21–S25, 2008.

## Appendix A

Each entry in the first table corresponds to a camera with unique resolution and quantization table. Each entry in the second table corresponds to an equivalence class of identical resolution and quantization table. The size of the equivalence class is in the first column, and the camera make and model and resolution are in the second column.

<p>Apple iPhone (1200 1600)  BenQ DC E43 (1704 2272)  Canon DIGITAL IXUS 40 (852 1136)  Canon DIGITAL IXUS 55 (1536 2048)  Canon DIGITAL IXUS 850 IS (1262 1600)  Canon DIGITAL IXUS 970 IS (852 1136)  Canon EOS 1000D (1296 1944)  Canon EOS-1D Mark II (2336 3504)  Canon EOS-1D Mark III (2584 3888)  Canon EOS-1D Mark III (684 1024)  Canon EOS-1D Mark II N (2346 3510)  Canon EOS-1Ds Mark II (2666 4000)  Canon EOS 20D (1166 1752)  Canon EOS 20D (2035 3057)  Canon EOS 20D (320 480)  Canon EOS 20D (426 640)  Canon EOS 30D (1166 1752)  Canon EOS 30D (1479 2048)  Canon EOS 30D (2346 3519)  Canon EOS 30D (594 890)  Canon EOS 30D (684 1024)  Canon EOS 30D (696 1044)  Canon EOS 30D (817 1226)  Canon EOS 350D DIGITAL (400 600)  Canon EOS 350D DIGITAL (534 800)  Canon EOS 350D DIGITAL (582 874)  Canon EOS 350D DIGITAL (691 1037)  Canon EOS 350D DIGITAL (800 1200)  Canon EOS 400D DIGITAL (1066 1600)  Canon EOS 400D DIGITAL (1288 1936)  Canon EOS 400D DIGITAL (1880 2816)  Canon EOS 400D DIGITAL (2592 3888)  Canon EOS 400D DIGITAL (511 768)  Canon EOS 400D DIGITAL (600 600)  Canon EOS 400D DIGITAL (683 1024)  Canon EOS 400D DIGITAL (778 1166)  Canon EOS 400D DIGITAL (892 1280)  Canon EOS 40D (1293 1946)  Canon EOS 40D (1364 2047)  Canon EOS 40D (1366 2048)  Canon EOS 40D (1980 2800)  Canon EOS 40D (2592 3888)  Canon EOS 40D (493 740)  Canon EOS 40D (576 864)  Canon EOS 40D (849 1200)  Canon EOS 40D (859 1289)  Canon EOS 450D (2056 3088)  Canon EOS 450D (569 836)  Canon EOS 450D (853 1280)  Canon EOS 5D (1000 1500)  Canon EOS 5D (1595 2400)  Canon EOS 5D (2112 3168)  Canon EOS 5D (2906 4372)  Canon EOS 5D (427 640)  Canon EOS 5D (546 700)  Canon EOS 5D (832 1248)  Canon EOS DIGITAL REBEL (1360 2048)  Canon EOS DIGITAL REBEL (717 1075)  Canon EOS DIGITAL REBEL XSi (1054 1581)  Canon EOS DIGITAL REBEL XSi (2239 2800)  Canon EOS DIGITAL REBEL XSi (700 1050)  Canon EOS DIGITAL REBEL XT (1192 1768)  Canon EOS DIGITAL REBEL XT (1866 2800)  Canon EOS DIGITAL REBEL XT (2308 3468)  Canon EOS DIGITAL REBEL XT (356 534)  Canon EOS DIGITAL REBEL XT (667 1000)  Canon EOS DIGITAL REBEL XT (683 1024)  Canon EOS DIGITAL REBEL XT (758 1140)  Canon EOS DIGITAL REBEL XT (1024 1536)  Canon EOS DIGITAL REBEL XT (1294 1944)  Canon EOS DIGITAL REBEL XT (1467 2200)  Canon EOS DIGITAL REBEL XT (2000 3000)  Canon EOS DIGITAL REBEL XT (2592 3888)  Canon EOS DIGITAL REBEL XT (320 480)  Canon EOS DIGITAL REBEL XT (480 720)  Canon EOS DIGITAL REBEL XT (559 800)  Canon EOS DIGITAL REBEL XT (666 1000)  Canon EOS DIGITAL REBEL XT (854 1280)  Canon EOS DIGITAL REBEL XT (902 1328)  Canon EOS DIGITAL REBEL XT (940 1408)  Canon EOS Kiss X2 (1365 2048)  Canon IXY DIGITAL 910 IS (336 448)  Canon PowerShot A300 (768 1024)  Canon PowerShot A430 (1363 1818)  Canon PowerShot A460 (1944 2592)  Canon PowerShot A530 (1456 2592)  Canon PowerShot A540 (1267 1689)  Canon PowerShot A570 IS (2250 3000)  Canon PowerShot A590 IS (2174 3262)  Canon PowerShot A620 (800 1067)  Canon PowerShot A640 (750 1000)  Canon PowerShot A710 IS (900 1200)  Canon PowerShot A720 IS (571 800)  Canon PowerShot A75 (1200 1600)  Canon PowerShot A80 (444 591)</p>	<p>Apple iPhone (599 800)  BenQ DC E43 (480 640)  Canon DIGITAL IXUS 50 (961 1280)  Canon DIGITAL IXUS 700 (563 750)  Canon DIGITAL IXUS 860 IS (718 1279)  Canon DIGITAL IXUS v2 (768 1024)  Canon EOS 1000D (2592 3888)  Canon EOS-1D Mark III (1107 1772)  Canon EOS-1D Mark III (2592 3888)  Canon EOS-1D Mark III (738 1181)  Canon EOS-1Ds (1352 2032)  Canon EOS-1Ds Mark II (2667 4000)  Canon EOS 20D (1168 1752)  Canon EOS 20D (2332 3504)  Canon EOS 20D (400 600)  Canon EOS 20D (496 730)  Canon EOS 30D (1364 2048)  Canon EOS 30D (1696 2544)  Canon EOS 30D (299 448)  Canon EOS 30D (639 960)  Canon EOS 30D (689 1030)  Canon EOS 30D (744 1024)  Canon EOS 350D DIGITAL (1152 1728)  Canon EOS 350D DIGITAL (427 640)  Canon EOS 350D DIGITAL (535 802)  Canon EOS 350D DIGITAL (682 1024)  Canon EOS 350D DIGITAL (726 1040)  Canon EOS 350D DIGITAL (851 1280)  Canon EOS 400D DIGITAL (1069 1600)  Canon EOS 400D DIGITAL (1296 1944)  Canon EOS 400D DIGITAL (1910 2846)  Canon EOS 400D DIGITAL (400 600)  Canon EOS 400D DIGITAL (512 768)  Canon EOS 400D DIGITAL (600 900)  Canon EOS 400D DIGITAL (725 1068)  Canon EOS 400D DIGITAL (778 1167)  Canon EOS 40D (1200 1920)  Canon EOS 40D (1296 1944)  Canon EOS 40D (1364 2048)  Canon EOS 40D (1555 2333)  Canon EOS 40D (2586 3892)  Canon EOS 40D (2602 3908)  Canon EOS 40D (500 750)  Canon EOS 40D (680 1020)  Canon EOS 40D (852 1280)  Canon EOS 450D (1420 2136)  Canon EOS 450D (2848 4272)  Canon EOS 450D (599 900)  Canon EOS 50D (1568 2352)  Canon EOS 5D (1453 2186)  Canon EOS 5D (1664 2496)  Canon EOS 5D (213 320)  Canon EOS 5D (2912 4368)  Canon EOS 5D (480 720)  Canon EOS 5D (798 1200)  Canon EOS D30 (1440 2160)  Canon EOS DIGITAL REBEL (2048 3072)  Canon EOS DIGITAL REBEL Xs (500 750)  Canon EOS DIGITAL REBEL XSi (1424 2136)  Canon EOS DIGITAL REBEL XSi (2848 4272)  Canon EOS DIGITAL REBEL XT (1149 1728)  Canon EOS DIGITAL REBEL XT (1365 2048)  Canon EOS DIGITAL REBEL XT (230 346)  Canon EOS DIGITAL REBEL XT (299 300)  Canon EOS DIGITAL REBEL XT (427 640)  Canon EOS DIGITAL REBEL XT (680 1024)  Canon EOS DIGITAL REBEL XT (691 1036)  Canon EOS DIGITAL REBEL XT (800 1200)  Canon EOS DIGITAL REBEL XT (1067 1600)  Canon EOS DIGITAL REBEL XT (1296 1944)  Canon EOS DIGITAL REBEL XT (1880 2816)  Canon EOS DIGITAL REBEL XT (2072 2588)  Canon EOS DIGITAL REBEL XT (2598 3900)  Canon EOS DIGITAL REBEL XT (333 500)  Canon EOS DIGITAL REBEL XT (519 778)  Canon EOS DIGITAL REBEL XT (572 800)  Canon EOS DIGITAL REBEL XT (667 1000)  Canon EOS DIGITAL REBEL XT (855 1280)  Canon EOS DIGITAL REBEL XT (907 1361)  Canon EOS Kiss Digital N (853 1280)  Canon IXY DIGITAL 50 (1704 2272)  Canon OPTURA600 (1736 2304)  Canon PowerShot A40 (612 800)  Canon PowerShot A430 (525 700)  Canon PowerShot A50 (960 1280)  Canon PowerShot A530 (450 600)  Canon PowerShot A550 (300 400)  Canon PowerShot A570 IS (263 350)  Canon PowerShot A610 (320 427)  Canon PowerShot A630 (1832 3264)  Canon PowerShot A650 IS (300 400)  Canon PowerShot A720 IS (1066 1600)  Canon PowerShot A720 IS (799 1200)  Canon PowerShot A80 (1022 1363)  Canon PowerShot A80 (568 758)</p>	<p>Apple iPhone (600 800)  Canon DIGITAL IXUS (1200 1600)  Canon DIGITAL IXUS 50 (972 1296)  Canon DIGITAL IXUS 75 (375 500)  Canon DIGITAL IXUS 960 IS (1350 1800)  Canon ELURA100 (864 1152)  Canon EOS-1D (1070 1600)  Canon EOS-1D Mark III (2304 3456)  Canon EOS-1D Mark III (335 504)  Canon EOS-1D Mark II N (2336 3504)  Canon EOS-1Ds (2704 4064)  Canon EOS-1Ds Mark III (3744 5616)  Canon EOS 20D (1280 1920)  Canon EOS 20D (2336 3504)  Canon EOS 20D (408 600)  Canon EOS 20D (853 1280)  Canon EOS 30D (1365 2047)  Canon EOS 30D (2336 3504)  Canon EOS 30D (586 1044)  Canon EOS 30D (682 1024)  Canon EOS 30D (695 1044)  Canon EOS 30D (800 1600)  Canon EOS 350D DIGITAL (1664 2496)  Canon EOS 350D DIGITAL (484 726)  Canon EOS 350D DIGITAL (576 864)  Canon EOS 350D DIGITAL (683 1024)  Canon EOS 350D DIGITAL (787 1180)  Canon EOS 400D DIGITAL (1065 1600)  Canon EOS 400D DIGITAL (1200 1800)  Canon EOS 400D DIGITAL (1600 2400)  Canon EOS 400D DIGITAL (2329 3499)  Canon EOS 400D DIGITAL (427 640)  Canon EOS 400D DIGITAL (567 850)  Canon EOS 400D DIGITAL (681 1023)  Canon EOS 400D DIGITAL (768 1152)  Canon EOS 400D DIGITAL (800 1280)  Canon EOS 40D (1288 1936)  Canon EOS 40D (1363 2048)  Canon EOS 40D (1366 2047)  Canon EOS 40D (1880 2816)  Canon EOS 40D (2591 2592)  Canon EOS 40D (467 700)  Canon EOS 40D (532 800)  Canon EOS 40D (683 1024)  Canon EOS 40D (853 1280)  Canon EOS 450D (1667 2500)  Canon EOS 450D (514 772)  Canon EOS 450D (600 900)  Canon EOS 50D (3168 4752)  Canon EOS 5D (1456 2184)  Canon EOS 5D (1706 2560)  Canon EOS 5D (2400 3600)  Canon EOS 5D (3150 4724)  Canon EOS 5D (533 800)  Canon EOS 5D (800 1200)  Canon EOS DIGITAL REBEL (1020 1536)  Canon EOS DIGITAL REBEL (480 600)  Canon EOS DIGITAL REBEL XSi (1028 1544)  Canon EOS DIGITAL REBEL XSi (2056 3088)  Canon EOS DIGITAL REBEL XSi (2860 4292)  Canon EOS DIGITAL REBEL XT (1152 1728)  Canon EOS DIGITAL REBEL XT (1664 2496)  Canon EOS DIGITAL REBEL XT (2304 3456)  Canon EOS DIGITAL REBEL XT (300 300)  Canon EOS DIGITAL REBEL XT (531 800)  Canon EOS DIGITAL REBEL XT (682 1024)  Canon EOS DIGITAL REBEL XT (692 1037)  Canon EOS DIGITAL REBEL XT (820 1024)  Canon EOS DIGITAL REBEL XT (1288 1936)  Canon EOS DIGITAL REBEL XT (1367 2048)  Canon EOS DIGITAL REBEL XT (1882 2800)  Canon EOS DIGITAL REBEL XT (2588 3888)  Canon EOS DIGITAL REBEL XT (2742 4038)  Canon EOS DIGITAL REBEL XT (427 640)  Canon EOS DIGITAL REBEL XT (533 800)  Canon EOS DIGITAL REBEL XT (599 800)  Canon EOS DIGITAL REBEL XT (800 1200)  Canon EOS DIGITAL REBEL XT (900 1328)  Canon EOS DIGITAL REBEL XT (934 1400)  Canon EOS Kiss Digital X (1367 2048)  Canon IXY DIGITAL 900 IS (662 800)  Canon PowerShot A20 (768 1024)  Canon PowerShot A430 (120 160)  Canon PowerShot A430 (600 800)  Canon PowerShot A530 (1439 1920)  Canon PowerShot A540 (1056 1408)  Canon PowerShot A560 (400 533)  Canon PowerShot A570 IS (576 768)  Canon PowerShot A610 (480 640)  Canon PowerShot A640 (1368 1824)  Canon PowerShot A710 IS (675 900)  Canon PowerShot A720 IS (480 640)  Canon PowerShot A720 IS (960 1200)  Canon PowerShot A80 (375 500)  Canon PowerShot A95 (666 999)</p>
--	---	--

Canon PowerShot G10 (2480 4416)  
Canon PowerShot G3 (738 1088)  
Canon PowerShot G7 (2048 3648)  
Canon PowerShot G9 (1500 2000)  
Canon PowerShot G9 (3000 4000)  
Canon PowerShot G9 (719 1280)  
Canon PowerShot S1 IS (1200 1600)  
Canon PowerShot S2 IS (720 960)  
Canon PowerShot S3 IS (2112 2816)  
Canon PowerShot S400 (592 800)  
Canon PowerShot S5 IS (1220 1620)  
Canon PowerShot S5 IS (840 1120)  
Canon PowerShot SD1000 (1282 1600)  
Canon PowerShot SD1000 (750 1000)  
Canon PowerShot SD1100 IS (2173 3264)  
Canon PowerShot SD1100 IS (2176 3264)  
Canon PowerShot SD200 (961 1600)  
Canon PowerShot SD300 (951 992)  
Canon PowerShot SD600 (1704 2272)  
Canon PowerShot SD700 IS (1584 2816)  
Canon PowerShot SD750 (482 640)  
Canon PowerShot SD750 (864 1536)  
Canon PowerShot SD800 IS (1152 1536)  
Canon PowerShot SD800 IS (1536 2304)  
Canon PowerShot SD800 IS (806 1075)  
Canon PowerShot SD870 IS (368 490)  
Canon PowerShot SX100 IS (2448 3264)  
Canon PowerShot SX100 IS (900 1200)  
Casio EX-S10 (900 1200)  
Casio EX-S880 (480 640)  
Casio EX-Z1000 (1536 2048)  
Casio EX-Z1050 (1571 2800)  
Casio EX-Z1050 (2736 3648)  
Casio EX-Z57 (1082 1402)  
Casio EX-Z60 (2112 2816)  
Casio EX-Z750 (367 490)  
Casio EX-Z75 (672 896)  
Casio EX-Z80 (2176 3264)  
Casio EX-Z85 (2592 3456)  
Digital Camera 9GF00 (2304 3072)  
DXG 409 (1728 2304)  
Fujifilm FinePix2800ZOOM (1200 1600)  
Fujifilm FinePix A345 (1200 1600)  
Fujifilm FinePix A360 (1536 2304)  
Fujifilm FinePix A500 (1944 2592)  
Fujifilm FinePix A820 (1200 1600)  
Fujifilm FinePix E900 (2616 3488)  
Fujifilm FinePix F30 (2136 2848)  
Fujifilm FinePix F40fd (2472 3296)  
Fujifilm FinePix F480 (750 1000)  
Fujifilm FinePix F50fd (3000 4000)  
Fujifilm FinePix F810 (1296 2304)  
Fujifilm FinePix S100FS (2880 3840)  
Fujifilm FinePix S5000 (1200 1600)  
Fujifilm FinePix S5100 (1704 2272)  
Fujifilm FinePix S5600 (1944 2592)  
Fujifilm FinePix S5700 S700 (2040 2040)  
Fujifilm FinePix S5800 S800 (2448 3264)  
Fujifilm FinePix S6000fd (2136 2848)  
Fujifilm FinePix S7000 (1538 2047)  
Fujifilm FinePix S9500 (1200 1600)  
Fujifilm FinePix S9600 (913 1280)  
Fujifilm FinePix Z10fd (1200 1600)  
Fujifilm FinePix Z1 (1944 2592)  
Fujifilm IS-1 (2616 3488)  
General Imaging A830 (2448 3264)  
Hewlett-Packard 635 Digital Camera (1200 1600)  
Hewlett-Packard PhotoSmart C945 (V01.60) (1952 2608)  
Hewlett-Packard Photosmart E427 (2136 2848)  
Hewlett-Packard Photosmart M537 (2128 2848)  
Hewlett-Packard PhotoSmart R707 (V01.00) (1952 2592)  
Hewlett-Packard PhotoSmart R717 (V01.00) (2144 2848)  
Hewlett-Packard PhotoSmart R717 (V01.00) (600 600)  
Hewlett-Packard PhotoSmart R727 (V01.00)+ (1728 2304)  
Hewlett-Packard PhotoSmart R817 (V01.00) (1536 2048)  
Hewlett-Packard Photosmart R960 (V01.00) (2736 3648)  
Hewlett-Packard Photosmart M407 (1704 2272)  
HTC Apache (240 320)  
HTC TITA100 (1200 1600)  
Kodak EASYSHARE Z1012 IS (1944 2592)  
Kodak EASYSHARE Z8612 IS (2448 3264)  
Konica Minolta DiMAGE A2 (1200 1600)  
Konica Minolta DiMAGE X1 (2448 3264)  
Konica Minolta DiMAGE Z3 (1704 2272)  
Konica Minolta DiMAGE Z6 (1704 2272)  
Konica Minolta MAXXUM 5D (1000 1504)  
Kyocera Finecam-L3v (480 640)  
Leica Digilux1 (1680 2240)  
Leica D-LUX 3 (1152 2048)  
Leica D-LUX 3 (2376 4224)  
LG Electronics KF750 (614 2048)  
Minolta DiMAGE 7 (1920 2560)  
Motorola MOTORAZR9V (1200 1600)  
NHJ Limited D'zign DV-5 (1800 2400)  
Nikon COOLPIX L1 (528 704)  
Nikon COOLPIX L3 (1944 2592)  
Nikon COOLPIX L4 (1704 2272)

Canon PowerShot G10 (3312 4416)  
Canon PowerShot G3 (826 1088)  
Canon PowerShot G7 (2736 3648)  
Canon PowerShot G9 (1535 2048)  
Canon PowerShot G9 (360 640)  
Canon PowerShot S10 (600 800)  
Canon PowerShot S1 IS (1536 2048)  
Canon PowerShot S3 IS (1200 1600)  
Canon PowerShot S3 IS (608 1080)  
Canon PowerShot S500 (875 1166)  
Canon PowerShot S5 IS (1440 1800)  
Canon PowerShot SD1000 (1280 1600)  
Canon PowerShot SD1000 (1728 3072)  
Canon PowerShot SD1000 (761 1014)  
Canon PowerShot SD1100 IS (2174 3264)  
Canon PowerShot SD1100 IS (449 800)  
Canon PowerShot SD200 (962 1600)  
Canon PowerShot SD400 (1944 2592)  
Canon PowerShot SD630 (1878 2816)  
Canon PowerShot SD750 (2304 2995)  
Canon PowerShot SD750 (600 800)  
Canon PowerShot SD750 (900 1200)  
Canon PowerShot SD800 IS (1200 1800)  
Canon PowerShot SD800 IS (1600 2400)  
Canon PowerShot SD850 IS (396 528)  
Canon PowerShot SD950 IS (2248 4000)  
Canon PowerShot SX100 IS (674 1200)  
Canon PowerShot SX110 IS (2592 3456)  
Casio EX-S600 (2112 2816)  
Casio EX-V8 (1728 2304)  
Casio EX-Z1000 (1920 2560)  
Casio EX-Z1050 (1920 2560)  
Casio EX-Z1080 (2048 3648)  
Casio EX-Z600 (1872 2816)  
Casio EX-Z70 (1920 2560)  
Casio EX-Z750 (600 800)  
Casio EX-Z77 (1536 2048)  
Casio EX-Z80 (396 528)  
Casio EX-Z9 (2448 3264)  
Digital Camera D55MP (960 1280)  
Fujifilm Digital Q1 (960 1280)  
Fujifilm FinePixA201 (1200 1600)  
Fujifilm FinePix A345 (1728 2304)  
Fujifilm FinePix A360 (266 400)  
Fujifilm FinePix A600 (1536 2048)  
Fujifilm FinePix A900 (2616 3488)  
Fujifilm FinePix F10 (2016 3024)  
Fujifilm FinePix F30 (600 800)  
Fujifilm FinePix F47fd (2616 3488)  
Fujifilm FinePix F50fd (1500 2000)  
Fujifilm FinePix F50SE (3000 4000)  
Fujifilm FinePix S1000fd (1803 2400)  
Fujifilm FinePixS2Pro (2016 3024)  
Fujifilm FinePix S5000 (1210 2816)  
Fujifilm FinePix S5200 (1944 2592)  
Fujifilm FinePix S5700 S700 (1152 1536)  
Fujifilm FinePix S5700 S700 (2048 3072)  
Fujifilm FinePix S5SPro (2848 4256)  
Fujifilm FinePix S602 ZOOM (960 1280)  
Fujifilm FinePix S7000 (3040 4048)  
Fujifilm FinePix S9500 (2616 3488)  
Fujifilm FinePix Z1000fd (1728 2304)  
Fujifilm FinePix Z10fd (1728 2304)  
Fujifilm FinePix Z5fd (1200 1600)  
Fujifilm Q1 DIGITAL 4.0 Ir (675 900)  
General Imaging A830 (768 1024)  
Hewlett-Packard PhotoSmart 43x series (1536 2048)  
Hewlett-Packard Photosmart E317 (1536 2048)  
Hewlett-Packard Photosmart M437 (1920 2576)  
Hewlett-Packard Photosmart M537 (956 1280)  
Hewlett-Packard PhotoSmart R707 (V01.00) (960 1280)  
Hewlett-Packard PhotoSmart R717 (V01.00) (452 600)  
Hewlett-Packard PhotoSmart R717 (V01.00)d (962 1280)  
Hewlett-Packard PhotoSmart R727 (V01.00) (960 1280)  
Hewlett-Packard PhotoSmart R817 (V01.00) (1936 2592)  
Hewlett-Packard Photosmart M305 (1536 2048)  
Hewlett-Packard Photosmart M417 (1536 2048)  
HTC Hermes (480 640)  
JVC GZ-MG21 (480 640)  
Kodak EASYSHARE Z1012 IS (2736 3648)  
Kodak Z612 ZOOM (2128 2832)  
Konica Minolta DiMAGE A2 (2440 3256)  
Konica Minolta DiMAGE Z2 (1704 2272)  
Konica Minolta DiMAGE Z5 (1920 2560)  
Konica Minolta DiMAGE Z6 (2112 2816)  
Konica Minolta MAXXUM 5D (1496 2256)  
Leica Camera AG M8 Digital Camera (2624 3936)  
Leica DIGILUX 2 (1912 2552)  
Leica D-LUX 3 (2376 3168)  
Leica D-LUX 3 (576 1024)  
LG Electronics KU990 (480 640)  
Minolta DiMAGE 7i (1920 2560)  
Motorola MOTOZ9 (1200 1600)  
Nikon COOLPIX L11 (384 512)  
Nikon COOLPIX L18 (1944 2592)  
Nikon COOLPIX L3 (538 717)  
Nikon COOLPIX L5 (2304 3072)

Canon PowerShot G3 (571 838)  
Canon PowerShot G5 (1166 1555)  
Canon PowerShot G9 (1151 2048)  
Canon PowerShot G9 (2250 3000)  
Canon PowerShot G9 (576 768)  
Canon PowerShot S10 (960 1280)  
Canon PowerShot S2 IS (450 600)  
Canon PowerShot S3 IS (1584 2816)  
Canon PowerShot S400 (1704 2272)  
Canon PowerShot S5 IS (1050 1400)  
Canon PowerShot S5 IS (1832 3264)  
Canon PowerShot SD1000 (1281 1600)  
Canon PowerShot SD1000 (2304 3072)  
Canon PowerShot SD1100 IS (1832 3264)  
Canon PowerShot SD1100 IS (2175 3264)  
Canon PowerShot SD200 (1536 2048)  
Canon PowerShot SD300 (375 500)  
Canon PowerShot SD550 (768 960)  
Canon PowerShot SD630 (675 900)  
Canon PowerShot SD750 (300 400)  
Canon PowerShot SD750 (750 1000)  
Canon PowerShot SD800 IS (1024 1536)  
Canon PowerShot SD800 IS (1400 2100)  
Canon PowerShot SD800 IS (1800 2400)  
Canon PowerShot SD870 IS (360 480)  
Canon PowerShot SX100 IS (2100 2800)  
Canon PowerShot SX100 IS (808 1078)  
Casio EX-F1 (1200 1600)  
Casio EX-S880 (2176 3264)  
Casio EX-V8 (2448 3264)  
Casio EX-Z1050 (1536 2048)  
Casio EX-Z1050 (2048 3648)  
Casio EX-Z40 (480 640)  
Casio EX-Z60 (1872 2816)  
Casio EX-Z70 (2304 3072)  
Casio EX-Z75 (2304 3072)  
Casio EX-Z77 (2304 3072)  
Casio EX-Z850 (2176 3264)  
Digital Camera 5MP-9ER (2448 3264)  
DSCimg Cameras (1760 1760)  
Fujifilm FinePix2400Zoom (1200 1600)  
Fujifilm FinePix A330 (1512 2016)  
Fujifilm FinePix A350 (1944 2592)  
Fujifilm FinePix A360 (480 640)  
Fujifilm FinePix A610 (1175 1567)  
Fujifilm FinePix E550 (2136 2848)  
Fujifilm FinePix F10 (2136 2848)  
Fujifilm FinePix F31fd (2136 2848)  
Fujifilm FinePix F480 (1728 2304)  
Fujifilm FinePix F50fd (1650 2200)  
Fujifilm FinePix F650 (2112 2816)  
Fujifilm FinePix S1000fd (2736 3648)  
Fujifilm FinePix S3100 (480 640)  
Fujifilm FinePix S5000 (960 1280)  
Fujifilm FinePix S5500 (1125 1500)  
Fujifilm FinePix S5700 S700 (1728 2304)  
Fujifilm FinePix S5700 S700 (2304 3072)  
Fujifilm FinePix S6000fd (2016 3024)  
Fujifilm FinePix S6500fd (2136 2848)  
Fujifilm FinePix S8000fd (2448 3264)  
Fujifilm FinePix S9600 (600 800)  
Fujifilm FinePix Z100fd (2448 3264)  
Fujifilm FinePix Z10fd (2304 3072)  
Fujifilm FinePix Z5fd (2136 2848)  
General Imaging A730 (2304 3072)  
General Imaging E1035 (2052 3648)  
Hewlett-Packard PhotoSmart 43x series (1586 2098)  
Hewlett-Packard Photosmart E317 (1920 2560)  
Hewlett-Packard Photosmart M440 (1920 2576)  
Hewlett-Packard Photosmart M540 (2136 2848)  
Hewlett-Packard PhotoSmart R717 (V01.00) (1542 2048)  
Hewlett-Packard PhotoSmart R717 (V01.00) (480 640)  
Hewlett-Packard PhotoSmart R725 (V01.00)+ (2144 2848)  
Hewlett-Packard Photosmart R740 (2320 3088)  
Hewlett-Packard PhotoSmart R927 (V01.00)d (2480 3296)  
Hewlett-Packard Photosmart M305 (960 1280)  
Hewlett-Packard Photosmart M417 (606 800)  
HTC HTC-Touch (240 320)  
Kodak DX6340 ZOOM (1524 2032)  
Kodak EASYSHARE Z1485 IS (3264 4352)  
Konica Minolta DiMAGE A200 (2448 3264)  
Konica Minolta DiMAGE A2 (2448 3264)  
Konica Minolta DiMAGE Z3 (1200 1600)  
Konica Minolta DiMAGE Z6 (1200 1600)  
Konica Minolta DiMAGE Z6 (516 600)  
Konica Minolta MAXXUM 7D (1992 3000)  
Leica C-LUX 2 (1920 2560)  
Leica DIGILUX 2 (1920 2560)  
Leica D-LUX 3 (2376 3568)  
LG Electronics (960 1280)  
Minolta DiMAGE 5 (1536 2048)  
Minolta DiMAGE Z1 (614 819)  
Motorola RAZRV3xx (1024 1280)  
Nikon COOLPIX L1 (2112 2816)  
Nikon COOLPIX L18 (2448 3264)  
Nikon COOLPIX L3 (768 1024)  
Nikon COOLPIX L6 (2112 2816)

Nikon COOLPIX P3 (2448 3264)  
Nikon COOLPIX P4 (768 1024)  
Nikon COOLPIX P80 (2736 3648)  
Nikon COOLPIX S210 (2448 3264)  
Nikon COOLPIX S51 (2448 3264)  
Nikon D100 (2008 3020)  
Nikon D1 (1312 2000)  
Nikon D200 (1040 1554)  
Nikon D200 (1272 1900)  
Nikon D200 (1369 2048)  
Nikon D200 (1944 2896)  
Nikon D200 (2608 3880)  
Nikon D200 (482 720)  
Nikon D200 (536 800)  
Nikon D200 (803 1200)  
Nikon D2H (1632 2464)  
Nikon D2Hs (3378 5100)  
Nikon D300 (1065 1600)  
Nikon D300 (1151 2048)  
Nikon D300 (1357 2048)  
Nikon D300 (1426 2152)  
Nikon D300 (1859 2800)  
Nikon D300 (2852 4304)  
Nikon D300 (478 720)  
Nikon D300 (531 800)  
Nikon D300 (679 1024)  
Nikon D300 (729 1024)  
Nikon D300 (732 1024)  
Nikon D300 (804 804)  
Nikon D300 (871 1280)  
Nikon D3 (2828 4272)  
Nikon D40 (1000 1504)  
Nikon D40 (1496 2256)  
Nikon D40 (1877 2800)  
Nikon D40 (1998 3024)  
Nikon D40 (2140 3148)  
Nikon D40 (477 720)  
Nikon D40 (533 800)  
Nikon D40 (681 1024)  
Nikon D40 (817 1024)  
Nikon D40 (820 1024)  
Nikon D40X (1037 1549)  
Nikon D40X (1296 1936)  
Nikon D40X (321 480)  
Nikon D40X (578 864)  
Nikon D40X (685 1024)  
Nikon D50 (1064 1600)  
Nikon D50 (2000 3008)  
Nikon D50 (300 452)  
Nikon D50 (661 1000)  
Nikon D50 (798 1200)  
Nikon D60 (1295 1936)  
Nikon D60 (2592 3872)  
Nikon D60 (803 1200)  
Nikon D700 (1362 2048)  
Nikon D700 (2832 4256)  
Nikon D70 (318 480)  
Nikon D70 (321 480)  
Nikon D70 (480 761)  
Nikon D70 (680 1024)  
Nikon D70 (847 1250)  
Nikon D70 (864 1300)  
Nikon D70 (999 1512)  
Nikon D70s (521 702)  
Nikon D80 (1070 1600)  
Nikon D80 (1075 1600)  
Nikon D80 (1296 1936)  
Nikon D80 (1874 2800)  
Nikon D80 (2592 3872)  
Nikon D80 (2694 3974)  
Nikon D80 (429 639)  
Nikon D80 (486 724)  
Nikon D80 (594 960)  
Nikon D80 (648 968)  
Nikon D80 (682 960)  
Nikon D80 (687 1024)  
Nikon D80 (859 1280)  
Nikon D90 (1424 2144)  
Nikon D90 (800 1200)  
Nikon E4100 (1712 2288)  
Nikon E4600 (599 800)  
Nikon E5200 (1944 2592)  
Nikon E5700 (1920 2560)  
Nikon E7600 (480 640)  
Nikon E8700 (2448 3264)  
Nikon E885 (768 1024)  
Nokia 6120c (864 1152)  
Olympus C160,D395 (1536 2048)  
Olympus C4040Z (960 1280)  
Olympus C4100Z,C4000Z (1532 2047)  
Olympus C4100Z,C4000Z (2400 3200)  
Olympus C725UZ (1488 1984)  
Olympus C765UZ (575 768)  
Olympus C8080WZ (900 1200)  
Olympus E-300 (2448 3264)  
Olympus E-300 (960 1280)  
Olympus E-3 (525 700)

Nikon COOLPIX P4 (1944 2592)  
Nikon COOLPIX P5100 (3000 4000)  
Nikon COOLPIX P80 (330 440)  
Nikon COOLPIX S50 (2304 3072)  
Nikon COOLPIX S550 (2736 3648)  
Nikon D100 (425 640)  
Nikon D1X (1960 3008)  
Nikon D200 (1067 1600)  
Nikon D200 (1296 1936)  
Nikon D200 (1848 2723)  
Nikon D200 (2592 3872)  
Nikon D200 (382 564)  
Nikon D200 (483 720)  
Nikon D200 (685 1023)  
Nikon D200 (860 1280)  
Nikon D2H (678 1024)  
Nikon D300 (1062 1600)  
Nikon D300 (1066 1600)  
Nikon D300 (1153 2048)  
Nikon D300 (1360 2048)  
Nikon D300 (1599 1600)  
Nikon D300 (228 344)  
Nikon D300 (2868 4320)  
Nikon D300 (530 800)  
Nikon D300 (533 800)  
Nikon D300 (680 1024)  
Nikon D300 (730 1024)  
Nikon D300 (733 1024)  
Nikon D300 (848 1280)  
Nikon D3 (1356 2048)  
Nikon D3 (2832 4256)  
Nikon D40 (1241 1867)  
Nikon D40 (1516 2276)  
Nikon D40 (1903 2800)  
Nikon D40 (2000 3008)  
Nikon D40 (399 600)  
Nikon D40 (500 752)  
Nikon D40 (598 900)  
Nikon D40 (683 1024)  
Nikon D40 (818 1024)  
Nikon D40 (821 1024)  
Nikon D40X (1040 1555)  
Nikon D40X (1944 2896)  
Nikon D40X (5350 8000)  
Nikon D40X (648 968)  
Nikon D50 (1000 1504)  
Nikon D50 (1276 1920)  
Nikon D50 (2014 3039)  
Nikon D50 (424 640)  
Nikon D50 (665 1000)  
Nikon D60 (1069 1593)  
Nikon D60 (1713 2560)  
Nikon D60 (536 800)  
Nikon D700 (1118 1680)  
Nikon D700 (2120 3184)  
Nikon D70 (1064 1600)  
Nikon D70 (319 480)  
Nikon D70 (426 640)  
Nikon D70 (499 756)  
Nikon D70 (681 1024)  
Nikon D70 (851 1300)  
Nikon D70 (982 1500)  
Nikon D70s (1488 2240)  
Nikon D70s (600 903)  
Nikon D80 (1071 1600)  
Nikon D80 (1205 1800)  
Nikon D80 (1300 1944)  
Nikon D80 (1944 2896)  
Nikon D80 (2608 3880)  
Nikon D80 (402 600)  
Nikon D80 (429 640)  
Nikon D80 (514 768)  
Nikon D80 (600 900)  
Nikon D80 (669 999)  
Nikon D80 (685 1024)  
Nikon D80 (758 1097)  
Nikon D80 (892 1315)  
Nikon D90 (2848 4288)  
Nikon E2000 (480 640)  
Nikon E4600 (1712 2288)  
Nikon E4800 (1712 2288)  
Nikon E5200 (540 720)  
Nikon E5700 (852 1280)  
Nikon E7600 (768 1024)  
Nikon E8800 (612 816)  
Nikon E990 (750 1000)  
Nokia N96 (1944 2592)  
Olympus C170,D425 (1712 2288)  
Olympus C4100Z,C4000Z (1197 1600)  
Olympus C4100Z,C4000Z (1710 2280)  
Olympus C5050Z (1920 2560)  
Olympus C750UZ (1712 2288)  
Olympus C770UZ (1712 2288)  
Olympus D595Z,C500Z (1920 2560)  
Olympus E-300 (2464 3411)  
Olympus E-300 (962 1280)  
Olympus E-410 (1125 1500)

Nikon COOLPIX P4 (2448 3264)  
Nikon COOLPIX P60 (2448 3264)  
Nikon COOLPIX S10 (2112 2816)  
Nikon COOLPIX S50c (2304 3072)  
Nikon COOLPIX S9 (2112 2816)  
Nikon D100 (664 1000)  
Nikon D200 (1004 1500)  
Nikon D200 (1071 1600)  
Nikon D200 (1300 1942)  
Nikon D200 (1923 2872)  
Nikon D200 (2600 3884)  
Nikon D200 (428 640)  
Nikon D200 (484 720)  
Nikon D200 (685 1024)  
Nikon D2H (1224 1840)  
Nikon D2Hs (1632 2464)  
Nikon D300 (1063 1600)  
Nikon D300 (1141 1722)  
Nikon D300 (1328 2000)  
Nikon D300 (1424 2144)  
Nikon D300 (1600 1600)  
Nikon D300 (2848 4288)  
Nikon D300 (424 640)  
Nikon D300 (531 799)  
Nikon D300 (570 858)  
Nikon D300 (712 1072)  
Nikon D300 (731 1024)  
Nikon D300 (797 1200)  
Nikon D300 (850 1280)  
Nikon D3 (2120 3184)  
Nikon D3 (678 1024)  
Nikon D40 (1353 2048)  
Nikon D40 (1861 2800)  
Nikon D40 (1991 2930)  
Nikon D40 (2055 3008)  
Nikon D40 (427 640)  
Nikon D40 (532 800)  
Nikon D40 (679 1024)  
Nikon D40 (800 1203)  
Nikon D40 (819 1024)  
Nikon D40 (851 1280)  
Nikon D40X (1071 1600)  
Nikon D40X (2592 3872)  
Nikon D40X (535 800)  
Nikon D40X (678 1000)  
Nikon D50 (1061 1600)  
Nikon D50 (1496 2256)  
Nikon D50 (2659 4000)  
Nikon D50 (500 752)  
Nikon D50 (679 1024)  
Nikon D60 (1072 1600)  
Nikon D60 (1944 2896)  
Nikon D60 (736 1100)  
Nikon D700 (1361 2048)  
Nikon D700 (2828 4256)  
Nikon D70 (1488 2240)  
Nikon D70 (320 480)  
Nikon D70 (478 720)  
Nikon D70 (634 936)  
Nikon D70 (800 1203)  
Nikon D70 (863 1300)  
Nikon D70 (997 1500)  
Nikon D70s (519 702)  
Nikon D70s (850 1280)  
Nikon D80 (1074 1600)  
Nikon D80 (1250 1867)  
Nikon D80 (1374 2048)  
Nikon D80 (2020 2972)  
Nikon D80 (2613 3900)  
Nikon D80 (428 640)  
Nikon D80 (468 700)  
Nikon D80 (536 800)  
Nikon D80 (602 900)  
Nikon D80 (680 960)  
Nikon D80 (686 1024)  
Nikon D80 (853 1280)  
Nikon D80 (972 1448)  
Nikon D90 (797 1200)  
Nikon E3100 (1536 2048)  
Nikon E4600 (479 640)  
Nikon E4800 (766 1024)  
Nikon E5200 (768 1024)  
Nikon E7600 (1536 2048)  
Nikon E775 (1200 1600)  
Nikon E885 (1536 2048)  
Nikon E995 (600 800)  
Noritsu Koki QSS-32\_33 (2048 2079)  
Olympus C300Z,D550Z (1488 1984)  
Olympus C4100Z,C4000Z (1520 2288)  
Olympus C4100Z,C4000Z (1712 2288)  
Olympus C5060WZ (1296 1728)  
Olympus C765UZ (1712 2288)  
Olympus C8080WZ (1000 1326)  
Olympus D595Z,C500Z (480 480)  
Olympus E-300 (2595 3280)  
Olympus E-330 (2352 3136)  
Olympus E-410 (1279 1280)

Olympus E-410 (2681 3575)  
Olympus E-500 (1296 1728)  
Olympus E-510 (1368 1824)  
Olympus E-520 (1540 2047)  
Olympus FE280,X820,C520 (2448 3264)  
Olympus SP510UZ (2304 3072)  
Olympus u1010,S1010 (2736 3648)  
Olympus u1030SW,S1030SW (480 640)  
Olympus u30D,S410D,u410D (1536 2048)  
Olympus u710,S710 (1536 2048)  
Olympus u760,S760 (2304 3072)  
Olympus u770SW,S770SW (480 640)  
Olympus u790SW,S790SW (960 1280)  
Olympus u850SW,S850SW (1536 2048)  
Olympus uD600,S600 (1200 1600)  
Olympus X-3,C-60Z (2112 2816)  
Panasonic DMC-F55 (2736 3648)  
Panasonic DMC-FX01 (2112 2816)  
Panasonic DMC-FX07 (480 640)  
Panasonic DMC-FX10 (2112 2816)  
Panasonic DMC-FX30 (1367 1823)  
Panasonic DMC-FX30 (576 768)  
Panasonic DMC-FX37 (2056 3648)  
Panasonic DMC-FX50 (2048 3072)  
Panasonic DMC-FZ18 (1224 1632)  
Panasonic DMC-FZ18 (450 600)  
Panasonic DMC-FZ18 (819 1024)  
Panasonic DMC-FZ20 (1920 2560)  
Panasonic DMC-FZ28 (1536 2048)  
Panasonic DMC-FZ30 (1536 2048)  
Panasonic DMC-FZ30 (2160 3248)  
Panasonic DMC-FZ50 (2160 3248)  
Panasonic DMC-FZ5 (1200 1600)  
Panasonic DMC-FZ7 (1200 1600)  
Panasonic DMC-FZ7 (1880 2816)  
Panasonic DMC-FZ8 (1050 1400)  
Panasonic DMC-FZ8 (2304 3072)  
Panasonic DMC-LC20 (1200 1600)  
Panasonic DMC-LS2 (960 1280)  
Panasonic DMC-LS60 (1584 2816)  
Panasonic DMC-LX2 (1080 1920)  
Panasonic DMC-LX2 (2376 4224)  
Panasonic DMC-LX2 (808 1420)  
Panasonic DMC-LX3 (1335 2000)  
Panasonic DMC-LX3 (2520 3776)  
Panasonic DMC-LZ3 (1920 2560)  
Panasonic DMC-LZ6 (1728 3072)  
Panasonic DMC-LZ8 (1536 2048)  
Panasonic DMC-TZ1 (857 1200)  
Panasonic DMC-TZ3 (1200 1600)  
Panasonic DMC-TZ3 (1872 3328)  
Panasonic DMC-TZ3 (413 550)  
Panasonic DMC-TZ4 (1920 2560)  
Panasonic DMC-TZ5 (1036 1382)  
Panasonic DMC-TZ5 (1440 2560)  
Panasonic DMC-TZ5 (2592 3456)  
Pentax \*ist DS (2000 3008)  
Pentax K100D (736 1109)  
Pentax K10D (1249 1867)  
Pentax K10D (2000 3000)  
Pentax K10D (450 671)  
Pentax K10D (857 1280)  
Pentax K20D (1276 1920)  
Pentax Optio 330 (1536 2048)  
Pentax Optio 750Z (1539 2048)  
Pentax Optio MX (1536 2048)  
Pentax Optio S4 (1728 2304)  
Pentax Optio S6 (2112 2816)  
Pentax Optio SV (1920 2560)  
Research In Motion BlackBerry 8100 Series (480 640)  
Ricoh GR DIGITAL 2 (2432 3648)  
Ricoh GX200 (3000 4000)  
Samsung Digimax 301 (480 640)  
Samsung HMX20 (2160 2880)  
Samsung <KENOX S1050/S1050> (2736 3648)  
Samsung <NV3, VLUU NV3> (2304 3072)  
Samsung U-CA 4 Digital Camera (1704 2272)  
Samsung VLUU L837/ L83T (480 640)  
Samsung VLUU NV 7, NV 7 (375 500)  
Sanyo E6 (326 448)  
Sanyo E6 (332 448)  
Sanyo VPC-S500 (960 1280)  
Sony CD MAVICA (1704 2272)  
Sony CYBERSHOT (1704 2272)  
Sony CYBERSHOT (578 800)  
Sony CYBERSHOT U (1224 1632)  
Sony DCR-PC100 (294 300)  
Sony DCR-SR200 (1296 2304)  
Sony DSC-F828 (2448 3264)  
Sony DSC-H1 (1728 2592)  
Sony DSC-H2 (528 704)  
Sony DSC-H50 (576 1024)  
Sony DSC-H5 (1875 2500)  
Sony DSC-H7 (2176 3264)  
Sony DSC-N2 (2736 3648)  
Sony DSC-P200 (2048 3072)  
Sony DSC-P32 (1360 2048)

Olympus E-420 (2160 2880)  
Olympus E-500 (857 1143)  
Olympus E-510 (2736 3648)  
Olympus E-520 (2792 3712)  
Olympus SP350 (735 980)  
Olympus u1010,S1010 (1920 2560)  
Olympus u1030SW,S1030SW (2736 3648)  
Olympus u1200,S1200 (3000 4000)  
Olympus u700,S700 (2304 3072)  
Olympus u720SW,S720SW (1536 2048)  
Olympus u770SW,S770SW (2304 3072)  
Olympus u790SW,S790SW (2304 3072)  
Olympus u830,S830 (2448 3264)  
Olympus u850SW,S850SW (2448 3264)  
Olympus X100,D540Z,C310Z (1200 1600)  
Panasonic DMC-F55 (2432 3648)  
Panasonic DMC-FX01 (1360 2048)  
Panasonic DMC-FX07 (1728 3072)  
Panasonic DMC-FX100 (3000 4000)  
Panasonic DMC-FX30 (1352 1802)  
Panasonic DMC-FX30 (2048 3072)  
Panasonic DMC-FX33 (1440 2560)  
Panasonic DMC-FX50 (1728 3072)  
Panasonic DMC-FZ10 (1728 2304)  
Panasonic DMC-FZ18 (2448 3264)  
Panasonic DMC-FZ18 (818 1024)  
Panasonic DMC-FZ20 (1536 2048)  
Panasonic DMC-FZ20 (960 1280)  
Panasonic DMC-FZ30 (1024 1280)  
Panasonic DMC-FZ30 (1920 2560)  
Panasonic DMC-FZ3 (240 320)  
Panasonic DMC-FZ50 (2736 3648)  
Panasonic DMC-FZ5 (1920 2560)  
Panasonic DMC-FZ7 (1360 2048)  
Panasonic DMC-FZ7 (2112 2816)  
Panasonic DMC-FZ8 (1080 1920)  
Panasonic DMC-FZ8 (535 800)  
Panasonic DMC-LC5 (840 1120)  
Panasonic DMC-LS60 (1050 1400)  
Panasonic DMC-L570 (1536 2048)  
Panasonic DMC-LX2 (1152 2048)  
Panasonic DMC-LX2 (576 1024)  
Panasonic DMC-LX2 (852 1280)  
Panasonic DMC-LX3 (1768 2656)  
Panasonic DMC-LX3 (854 1280)  
Panasonic DMC-LZ5 (2112 2816)  
Panasonic DMC-LZ7 (1536 2048)  
Panasonic DMC-TZ1 (1920 2560)  
Panasonic DMC-TZ1 (858 1200)  
Panasonic DMC-TZ3 (1440 2560)  
Panasonic DMC-TZ3 (2144 3216)  
Panasonic DMC-TZ3 (960 1280)  
Panasonic DMC-TZ4 (2176 3264)  
Panasonic DMC-TZ5 (1296 1728)  
Panasonic DMC-TZ5 (2088 3712)  
Pentacore DCZ 6.8 (596 795)  
Pentax \*ist DS2 (2000 3008)  
Pentax K100D (788 1050)  
Pentax K10D (1308 1948)  
Pentax K10D (2000 3008)  
Pentax K10D (671 1000)  
Pentax K10D (967 1280)  
Pentax K20D (3104 4672)  
Pentax Optio 330GS (1536 2048)  
Pentax Optio A10 (2448 3264)  
Pentax Optio S10 (1944 2592)  
Pentax Optio S55 (1536 2048)  
Pentax Optio S7 (1728 2304)  
Research In Motion BlackBerry 8100 Series (1024 1280)  
Research In Motion BlackBerry 8310 (1200 1600)  
Ricoh GR DIGITAL 2 (2736 2736)  
Ricoh R8 (2832 3744)  
Samsung Digimax 301 (768 1024)  
Samsung i70 (2304 3072)  
Samsung <KENOX S630/S630> (2112 2816)  
Samsung S85 (2448 3264)  
Samsung VLUU L100, M100/L100, M100 (1875 2500)  
Samsung VLUU NV10, NV10 (2016 2688)  
Sanyo C5 (2760 3680)  
Sanyo E6 (329 448)  
Sanyo E6 (334 448)  
SeaLife DC800 (480 640)  
Sony CYBERSHOT (1200 1600)  
Sony CYBERSHOT (1920 2560)  
Sony CYBERSHOT (600 800)  
Sony DCR-DVDS505 (1728 2304)  
Sony DCR-PC110 (480 640)  
Sony DCR-SR65 (864 1152)  
Sony DSC-F828 (759 1012)  
Sony DSC-H1 (576 768)  
Sony DSC-H3 (1080 1920)  
Sony DSC-H50 (596 795)  
Sony DSC-H5 (336 504)  
Sony DSC-H7 (371 495)  
Sony DSC-P100 (1728 2592)  
Sony DSC-P200 (384 512)  
Sony DSC-P43 (960 1280)

Olympus E-420 (2160 2880)  
Olympus E-500 (857 1143)  
Olympus E-510 (2736 3648)  
Olympus E-520 (2792 3712)  
Olympus SP350 (735 980)  
Olympus u1010,S1010 (1920 2560)  
Olympus u1030SW,S1030SW (2736 3648)  
Olympus u1200,S1200 (3000 4000)  
Olympus u700,S700 (2304 3072)  
Olympus u720SW,S720SW (1536 2048)  
Olympus u770SW,S770SW (2304 3072)  
Olympus u790SW,S790SW (2304 3072)  
Olympus u830,S830 (2448 3264)  
Olympus u850SW,S850SW (2448 3264)  
Olympus X100,D540Z,C310Z (1200 1600)  
Panasonic DMC-F55 (2432 3648)  
Panasonic DMC-FX01 (1360 2048)  
Panasonic DMC-FX07 (1728 3072)  
Panasonic DMC-FX100 (3000 4000)  
Panasonic DMC-FX30 (1352 1802)  
Panasonic DMC-FX30 (2048 3072)  
Panasonic DMC-FX33 (1440 2560)  
Panasonic DMC-FX50 (1728 3072)  
Panasonic DMC-FZ10 (1728 2304)  
Panasonic DMC-FZ18 (2448 3264)  
Panasonic DMC-FZ18 (818 1024)  
Panasonic DMC-FZ20 (1536 2048)  
Panasonic DMC-FZ20 (960 1280)  
Panasonic DMC-FZ30 (1024 1280)  
Panasonic DMC-FZ30 (1920 2560)  
Panasonic DMC-FZ3 (240 320)  
Panasonic DMC-FZ50 (2736 3648)  
Panasonic DMC-FZ5 (960 1280)  
Panasonic DMC-FZ7 (1728 2304)  
Panasonic DMC-FZ7 (336 448)  
Panasonic DMC-FZ8 (2048 3072)  
Panasonic DMC-FZ8 (864 1152)  
Panasonic DMC-LS2 (1920 2560)  
Panasonic DMC-LS60 (1125 1500)  
Panasonic DMC-LX1 (2160 3840)  
Panasonic DMC-LX2 (2376 3168)  
Panasonic DMC-LX2 (720 1280)  
Panasonic DMC-LX3 (1125 2000)  
Panasonic DMC-LX3 (2232 3968)  
Panasonic DMC-LZ1 (1728 2304)  
Panasonic DMC-LZ5 (534 800)  
Panasonic DMC-LZ7 (2304 3072)  
Panasonic DMC-TZ1 (856 1200)  
Panasonic DMC-TZ2 (768 1024)  
Panasonic DMC-TZ3 (1712 2560)  
Panasonic DMC-TZ3 (2304 3072)  
Panasonic DMC-TZ4 (1840 3264)  
Panasonic DMC-TZ4 (2448 3264)  
Panasonic DMC-TZ5 (1440 1920)  
Panasonic DMC-TZ5 (2368 3552)  
Pentax \*ist DL (1600 2400)  
Pentax K100D (695 1050)  
Pentax K10D (1216 1824)  
Pentax K10D (2000 2988)  
Pentax K10D (2592 3872)  
Pentax K10D (823 1220)  
Pentax K200D (2592 3872)  
Pentax K20D (680 1024)  
Pentax Optio 430 (840 1120)  
Pentax Optio L40 (1944 2592)  
Pentax Optio S (1536 2048)  
Pentax Optio S5z (1200 1600)  
Pentax Optio S7 (2304 3072)  
Research In Motion BlackBerry 8100 Series (384 480)  
Research In Motion BlackBerry 8330 (768 1024)  
Ricoh GR DIGITAL 2 (2736 3648)  
Samsung Digimax 301 (1200 1600)  
Samsung Digimax S500/Kenox S500/Digimax 530 (1944 2592)  
Samsung I8510 (2448 3264)  
Samsung NV24HD, VLUU NV24HD, NV106HD (2736 3648)  
Samsung SPH-A800 (1224 1632)  
Samsung <VLUU L730/L730> (674 899)  
Samsung VLUU NV10, NV10 (806 1075)  
Sanyo E6 (325 448)  
Sanyo E6 (331 448)  
Sanyo E6 (335 448)  
Sigma DP1 (1760 2640)  
Sony CYBERSHOT (1360 2048)  
Sony CYBERSHOT (480 640)  
Sony CYBERSHOT (960 1280)  
Sony DCR-HC32E (480 640)  
Sony DCR-PC330 (1512 2016)  
Sony DSC-F828 (1944 2592)  
Sony DSC-H10 (729 972)  
Sony DSC-H1 (960 1280)  
Sony DSC-H50 (2592 3456)  
Sony DSC-H5 (1500 2000)  
Sony DSC-H5 (525 700)  
Sony DSC-N2 (1224 1632)  
Sony DSC-P150 (996 1316)  
Sony DSC-P200 (691 922)  
Sony DSC-P72 (1536 2048)

Sony DSC-P72 (689 918)	Sony DSC-P72 (918 1224)	Sony DSC-P73 (1536 2048)
Sony DSC-P73 (1728 2304)	Sony DSC-P73 (480 640)	Sony DSC-P73 (557 742)
Sony DSC-P92 (1944 2592)	Sony DSC-P93 (1536 2048)	Sony DSC-R1 (1856 2784)
Sony DSC-R1 (864 1296)	Sony DSC-S40 (1728 2304)	Sony DSC-S600 (1536 2048)
Sony DSC-S60 (1536 2304)	Sony DSC-S650 (1944 2592)	Sony DSC-S700 (375 500)
Sony DSC-S730 (467 700)	Sony DSC-S750 (1125 1500)	Sony DSC-S750 (2304 3072)
Sony DSC-T1 (480 640)	Sony DSC-T1 (504 672)	Sony DSC-T200 (1080 1920)
Sony DSC-T200 (1130 1970)	Sony DSC-T200 (2176 3264)	Sony DSC-T2 (580 740)
Sony DSC-T300 (2056 3648)	Sony DSC-T300 (2432 3648)	Sony DSC-T300 (768 1024)
Sony DSC-T30 (495 800)	Sony DSC-T3 (195 260)	Sony DSC-T5 (480 640)
Sony DSC-T700 (2736 3648)	Sony DSC-T70 (2176 3264)	Sony DSC-T70 (734 979)
Sony DSC-T9 (1063 1600)	Sony DSC-T9 (480 640)	Sony DSC-T9 (712 950)
Sony DSC-V3 (771 1028)	Sony DSC-W130 (1840 3264)	Sony DSC-W200 (2672 4000)
Sony DSC-W200 (3000 4000)	Sony DSC-W200 (780 1040)	Sony DSC-W300 (3168 4224)
Sony DSC-W35 (1224 1632)	Sony DSC-W35 (2048 3072)	Sony DSC-W50 (1872 2816)
Sony DSC-W50 (2112 2816)	Sony DSC-W50 (351 528)	Sony DSC-W50 (468 704)
Sony DSC-W5 (1944 2592)	Sony DSC-W55 (2304 3072)	Sony DSC-W55 (750 1000)
Sony DSC-W55 (820 1229)	Sony DSC-W70 (640 853)	Sony DSC-W80 (2048 3072)
Sony DSC-W80 (480 640)	Sony DSC-W90 (480 640)	Sony DSLR-A100 (1280 1920)
Sony DSLR-A100 (1292 1932)	Sony DSLR-A100 (2584 3864)	Sony DSLR-A100 (2592 3872)
Sony DSLR-A100 (546 800)	Sony DSLR-A200 (1122 1680)	Sony DSLR-A200 (1292 1932)
Sony DSLR-A200 (1936 2896)	Sony DSLR-A200 (2168 2615)	Sony DSLR-A300 (2584 3860)
Sony DSLR-A350 (1064 1600)	Sony DSLR-A350 (1520 2288)	Sony DSLR-A350 (1863 2800)
Sony DSLR-A350 (2272 3408)	Sony DSLR-A350 (2576 4592)	Sony DSLR-A350 (3056 4592)
Sony DSLR-A700 (2064 3104)	Sony DSLR-A700 (2848 4272)	Sony DSLR-A700 (513 640)
Sony DSLR-A700 (534 800)	Sony Ericsson K770i (1536 2048)	Sony Ericsson K770i (1538 2048)
Sony Ericsson K770i (961 1280)	Sony Ericsson K800i (1224 1632)	Sony Ericsson K800i (1536 2048)
Sony Ericsson K800i (480 640)	Sony Ericsson K800i (960 1280)	Sony Ericsson K810i (1224 1632)
Sony Ericsson P1i (1536 2048)	SONY Ericsson P1i (864 1152)	Sony Ericsson S700i (675 900)
Sony Ericsson W660i (960 1280)	Sony Ericsson W810i (480 640)	Sony FDMAVICA (1104 1472)
Sony FDMAVICA (1242 1642)	Sony FDMAVICA (480 640)	Sony HDR-SR10 (1296 2304)
Sony HDR-SR11 (2070 3680)	Sony MVC-CD500 (1944 2592)	SQ Tech SQ908 MEGA-Cam (1024 1280)
Supra DC-8600 (1920 2560)	Supra SLIMLINE X6 (1704 2272)	Toshiba PDR-M700 (1536 2048)
Treo 755p (640 800)	Vivitar V3935 Digital Camera (384 512)	Vivitar Vivicam8300s (2448 3264)



2	BenQ DC E43 (960 1280) – Gateway DC-T50 (960 1280)
2	Canon DIGITAL IXUS 40 (600 800) – Ricoh Caplio GX100 (600 800)
2	Canon DIGITAL IXUS 500 (336 448) – Panasonic DMC-FZ7 (336 448)
2	Canon DIGITAL IXUS 75 (750 1000) – Canon PowerShot A720 IS (750 1000)
2	Canon DIGITAL IXUS 900Ti (2048 3648) – Canon PowerShot G7 (2048 3648)
2	Canon DIGITAL IXUS 970 IS (2736 3648) – Canon PowerShot A640 (2736 3648)
2	Canon EOS 1000D (800 1200) – Canon EOS DIGITAL REBEL XTi (800 1200)
2	Canon EOS 10D (850 1280) – Canon EOS DIGITAL REBEL (850 1280)
2	Canon EOS-1D Mark III (1288 1936) – Canon EOS 40D (1288 1936)
2	Canon EOS-1Ds Mark II (3000 4500) – Canon EOS 5D (3000 4500)
2	Canon EOS 20D (1168 1752) – Canon EOS 30D (1168 1752)
2	Canon EOS 20D (1696 2544) – Canon EOS 30D (1696 2544)
2	Canon EOS 20D (2332 3504) – Canon EOS 30D (2332 3504)
2	Canon EOS 20D (2336 3504) – Canon EOS 30D (2336 3504)
2	Canon EOS 20D (426 640) – Canon EOS 30D (426 640)
2	Canon EOS 300D DIGITAL (1024 1536) – Canon EOS DIGITAL REBEL (1024 1536)
2	Canon EOS 30D (1168 1752) – Canon EOS 20D (1168 1752)
2	Canon EOS 30D (1696 2544) – Canon EOS 20D (1696 2544)
2	Canon EOS 30D (2336 3504) – Canon EOS 20D (2336 3504)
2	Canon EOS 30D (466 700) – Canon EOS 40D (466 700)
2	Canon EOS 30D (685 1024) – Nikon D80 (685 1024)
2	Canon EOS 350D DIGITAL (1152 1728) – Canon EOS DIGITAL REBEL XT (1152 1728)
2	Canon EOS 350D DIGITAL (1365 2047) – Canon EOS DIGITAL REBEL XT (1365 2047)
2	Canon EOS 350D DIGITAL (1664 2496) – Canon EOS DIGITAL REBEL XT (1664 2496)
2	Canon EOS 350D DIGITAL (2298 3456) – Canon EOS DIGITAL REBEL XT (2298 3456)
2	Canon EOS 350D DIGITAL (2304 3456) – Canon EOS DIGITAL REBEL XT (2304 3456)
2	Canon EOS 350D DIGITAL (2314 3474) – Canon EOS DIGITAL REBEL XT (2314 3474)
2	Canon EOS 350D DIGITAL (427 640) – Canon EOS 400D DIGITAL (427 640)
2	Canon EOS 350D DIGITAL (534 800) – Panasonic DMC-FZ8 (534 800)
2	Canon EOS 350D DIGITAL (853 1280) – Canon EOS 40D (853 1280)
2	Canon EOS 400D DIGITAL (1067 1600) – Nikon D300 (1067 1600)
2	Canon EOS 400D DIGITAL (1294 1944) – Canon EOS DIGITAL REBEL XTi (1294 1944)
2	Canon EOS 400D DIGITAL (1880 2816) – Canon EOS 40D (1880 2816)
2	Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)
2	Canon EOS 400D DIGITAL (427 640) – Canon EOS DIGITAL REBEL XTi (427 640)
2	Canon EOS 400D DIGITAL (682 1024) – Canon EOS DIGITAL REBEL XT (682 1024)
2	Canon EOS 40D (1296 1944) – Canon EOS DIGITAL REBEL XTi (1296 1944)
2	Canon EOS 40D (1333 2000) – Canon EOS 50D (1333 2000)
2	Canon EOS 40D (1367 2048) – Canon EOS Kiss Digital X (1367 2048)
2	Canon EOS 40D (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)
2	Canon EOS 40D (320 480) – Canon EOS DIGITAL REBEL XT (320 480)
2	Canon EOS 40D (465 700) – Nikon D50 (465 700)
2	Canon EOS 450D (1363 2048) – Canon EOS DIGITAL REBEL XSi (1363 2048)
2	Canon EOS 450D (2056 3088) – Canon EOS DIGITAL REBEL XSi (2056 3088)
2	Canon EOS 450D (2848 4272) – Canon EOS DIGITAL REBEL XSi (2848 4272)
2	Canon EOS 450D (682 1024) – Canon EOS DIGITAL REBEL XT (682 1024)
2	Canon EOS 5D (427 640) – Canon EOS 30D (427 640)
2	Canon EOS 5D (799 1200) – Canon EOS 30D (799 1200)
2	Canon EOS DIGITAL REBEL (1024 1536) – Canon EOS 300D DIGITAL (1024 1536)
2	Canon EOS DIGITAL REBEL XSi (1504 2256) – Canon EOS 450D (1504 2256)
2	Canon EOS DIGITAL REBEL XSi (2848 4272) – Canon EOS 450D (2848 4272)
2	Canon EOS DIGITAL REBEL XT (1664 2496) – Canon EOS 350D DIGITAL (1664 2496)
2	Canon EOS DIGITAL REBEL XT (426 640) – Canon EOS Kiss Digital X (426 640)
2	Canon EOS DIGITAL REBEL XT (507 760) – Canon EOS 350D DIGITAL (507 760)
2	Canon EOS DIGITAL REBEL XT (534 800) – Canon EOS 400D DIGITAL (534 800)
2	Canon EOS DIGITAL REBEL XTi (1200 1800) – Canon EOS 5D (1200 1800)
2	Canon EOS DIGITAL REBEL XTi (1288 1936) – Canon EOS 40D (1288 1936)
2	Canon EOS DIGITAL REBEL XTi (1294 1944) – Canon EOS 400D DIGITAL (1294 1944)
2	Canon EOS DIGITAL REBEL XTi (1296 1944) – Canon EOS 40D (1296 1944)
2	Canon EOS DIGITAL REBEL XTi (1880 2816) – Canon EOS 400D DIGITAL (1880 2816)
2	Canon EOS DIGITAL REBEL XTi (2592 3888) – Canon EOS-1D Mark III (2592 3888)
2	Canon EOS DIGITAL REBEL XTi (2592 3888) – Canon EOS 400D DIGITAL (2592 3888)
2	Canon EOS DIGITAL REBEL XTi (400 600) – Canon EOS 350D DIGITAL (400 600)
2	Canon EOS DIGITAL REBEL XTi (854 1280) – Canon EOS 400D DIGITAL (854 1280)
2	Canon EOS Kiss Digital X (1869 2800) – Canon EOS DIGITAL REBEL XTi (1869 2800)
2	Canon EOS Kiss X2 (1424 2136) – Canon EOS DIGITAL REBEL XSi (1424 2136)
2	Canon EOS Kiss X2 (800 1200) – Canon EOS 5D (800 1200)
2	Canon IXY DIGITAL 3000 IS (3312 4416) – Canon PowerShot G10 (3312 4416)
2	Canon PowerShot A430 (600 800) – Canon PowerShot G9 (600 800)
2	Canon PowerShot A560 (1728 3072) – Canon PowerShot SD1000 (1728 3072)
2	Canon PowerShot A640 (525 700) – Sony DSC-S700 (525 700)
2	Canon PowerShot A650 IS (3000 4000) – Canon PowerShot G9 (3000 4000)
2	Canon PowerShot A700 (1200 1600) – Canon PowerShot G9 (1200 1600)
2	Canon PowerShot A710 IS (450 600) – Canon PowerShot A80 (450 600)
2	Canon PowerShot A720 IS (360 480) – Olympus u820,S820 (360 480)
2	Canon PowerShot A80 (675 900) – Canon PowerShot G2 (675 900)
2	Canon PowerShot A85 (1704 2272) – Canon PowerShot SD600 (1704 2272)
2	Canon PowerShot G10 (1200 1600) – Apple iPhone (1200 1600)
2	Canon PowerShot G9 (3000 4000) – Canon PowerShot A650 IS (3000 4000)
2	Canon PowerShot G9 (3000 4000) – Sony DSC-W200 (3000 4000)
2	Canon PowerShot G9 (450 800) – Panasonic DMC-LX2 (450 800)
2	Canon PowerShot S100 (1200 1600) – Canon DIGITAL IXUS (1200 1600)
2	Canon PowerShot S2 IS (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600)
2	Canon PowerShot S2 IS (1944 2592) – Sony DSC-P93 (1944 2592)
2	Canon PowerShot S5 IS (612 816) – Sony DSC-T20 (612 816)
2	Canon PowerShot S5 IS (900 1200) – Canon PowerShot A720 IS (900 1200)
2	Canon PowerShot SD1100 IS (480 640) – Sony DSC-P92 (480 640)
2	Canon PowerShot SD20 (360 480) – Canon PowerShot A460 (360 480)
2	Canon PowerShot SD700 IS (900 1200) – Canon PowerShot SD850 IS (900 1200)
2	Canon PowerShot SD800 IS (1728 3072) – Panasonic DMC-FX30 (1728 3072)
2	Canon PowerShot SD850 IS (1832 3264) – Canon PowerShot S5 IS (1832 3264)
2	Canon PowerShot SD870 IS (2448 3264) – Fujifilm FinePix J10 (2448 3264)
2	Canon PowerShot SD950 IS (2248 4000) – Canon PowerShot G9 (2248 4000)
2	Canon PowerShot SD990 IS (3312 4416) – Canon PowerShot G10 (3312 4416)
2	Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264)

2 Canon PowerShot SX10 IS (2048 3648) – Canon PowerShot G7 (2048 3648)  
 2 Casio COMPUTER EX-S600 (2112 2816) – Casio COMPUTER EX-Z60 (2112 2816)  
 2 Casio COMPUTER EX-S880 (2112 2816) – Casio COMPUTER EX-F1 (2112 2816)  
 2 Casio COMPUTER EX-Z1000 (1536 2048) – Casio COMPUTER EX-Z60 (1536 2048)  
 2 Casio COMPUTER EX-Z1050 (480 640) – Casio COMPUTER EX-S10 (480 640)  
 2 Casio EX-Z1080 (2048 3648) – Casio EX-S10 (2048 3648)  
 2 Casio EX-Z110 (2112 2816) – Casio EX-S600 (2112 2816)  
 2 Casio EX-Z70 (1920 2560) – Panasonic DMC-TZ3 (1920 2560)  
 2 Casio EX-Z70 (2304 3072) – Casio EX-S770 (2304 3072)  
 2 Casio EX-Z75 (2304 3072) – Casio EX-Z70 (2304 3072)  
 2 Casio EX-Z77 (2304 3072) – Casio EX-V7 (2304 3072)  
 2 Fujifilm Digital Q1 (480 640) – Samsung Digimax 301 (480 640)  
 2 Fujifilm FinePix2800ZOOM (1200 1600) – Fujifilm FinePix Z5fd (1200 1600)  
 2 Fujifilm FinePix A360 (1728 2304) – Fujifilm FinePix A345 (1728 2304)  
 2 Fujifilm FinePix A370 (1944 2592) – Fujifilm FinePix A350 (1944 2592)  
 2 Fujifilm FinePix E900 (2616 3488) – Fujifilm FinePix S9600 (2616 3488)  
 2 Fujifilm FinePix F10 (2136 2848) – Fujifilm FinePix S6500fd (2136 2848)  
 2 Fujifilm FinePix F30 (2136 2848) – Fujifilm FinePix F10 (2136 2848)  
 2 Fujifilm FinePix F31fd (2136 2848) – Fujifilm FinePix F10 (2136 2848)  
 2 Fujifilm FinePix F650 (2112 2816) – Pentax Optio WPi (2112 2816)  
 2 Fujifilm FinePix J10 (2448 3264) – Samsung I8510 (2448 3264)  
 2 Fujifilm FinePix S5700 S700 (2048 3072) – Sony DSC-W35 (2048 3072)  
 2 Fujifilm FinePix S5700 S700 (2304 3072) – Olympus FE230/X790 (2304 3072)  
 2 Fujifilm FinePix S6000fd (2136 2848) – Fujifilm FinePix F31fd (2136 2848)  
 2 Fujifilm FinePix S6500fd (2136 2848) – Fujifilm FinePix Z5fd (2136 2848)  
 2 Fujifilm FinePix S8000fd (2448 3264) – Canon PowerShot A630 (2448 3264)  
 2 Fujifilm FinePix S9500 (432 576) – Fujifilm FinePix S602 ZOOM (432 576)  
 2 Fujifilm FinePix S9600 (600 800) – Canon PowerShot SD600 (600 800)  
 2 Fujifilm FinePix Z100fd (2448 3264) – Fujifilm FinePix S8000fd (2448 3264)  
 2 Fujifilm FinePix Z10fd (1728 2304) – Fujifilm FinePix Z100fd (1728 2304)  
 2 Fujifilm FinePix Z1 (1944 2592) – Fujifilm FinePix A500 (1944 2592)  
 2 Fujifilm FinePix Z5fd (1200 1600) – Fujifilm FinePixA201 (1200 1600)  
 2 Fujifilm FinePix Z5fd (2136 2848) – Fujifilm FinePix S6500fd (2136 2848)  
 2 Hewlett-Packard Photosmart M517 (1952 2576) – Hewlett-Packard Photosmart M415 (1952 2576)  
 2 Hewlett-Packard PhotoSmart R817 (V01.00) (1936 2592) – Hewlett-Packard PhotoSmart R817 (V01.00)d (1936 2592)  
 2 Hewlett-Packard PhotoSmart R927 (V01.00)d (2480 3296) – Hewlett-Packard PhotoSmart R927 (V01.00) (2480 3296)  
 2 HTC Hermes (1024 1280) – Camera (1024 1280)  
 2 HTC Hermes (1200 1600) – Apple iPhone (1200 1600)  
 2 JVC GZ-MG330 (480 640) – Nikon E885 (480 640)  
 2 Kodak EASYSHARE C813 ZOOM DIGIT (1125 1500) – Canon PowerShot A720 IS (1125 1500)  
 2 Leica D-LUX 3 (1152 2048) – Nikon D300 (1152 2048)  
 2 Leica D-LUX 3 (1728 3072) – Panasonic DMC-LX2 (1728 3072)  
 2 Leica D-LUX 3 (2376 3168) – Panasonic DMC-LX2 (2376 3168)  
 2 Leica D-LUX 3 (2376 4224) – Panasonic DMC-LX2 (2376 4224)  
 2 LG Electronics KF750 (1536 2048) – LG Electronics KU990 (1536 2048)  
 2 LG Electronics KU990 (1200 1600) – LG Electronics KF750 (1200 1600)  
 2 Minolta DiMAGE F300 (1920 2560) – Nikon E5700 (1920 2560)  
 2 Minolta DiMAGE S404 (1704 2272) – Konica Minolta DiMAGE Z3 (1704 2272)  
 2 Nikon COOLPIX L1 (2112 2816) – Konica Minolta DiMAGE Z6 (2112 2816)  
 2 Nikon COOLPIX L12 (768 1024) – Nikon E7600 (768 1024)  
 2 Nikon COOLPIX L5 (2304 3072) – Sony DSC-S750 (2304 3072)  
 2 Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S10 (2112 2816)  
 2 Nikon COOLPIX P3 (2448 3264) – Nikon COOLPIX P4 (2448 3264)  
 2 Nikon COOLPIX P4 (1944 2592) – Nikon E5200 (1944 2592)  
 2 Nikon COOLPIX P4 (768 1024) – Nikon E5200 (768 1024)  
 2 Nikon COOLPIX P5100 (1536 2048) – Sony Ericsson K800i (1536 2048)  
 2 Nikon COOLPIX P5100 (3000 4000) – Olympus u1200,S1200 (3000 4000)  
 2 Nikon COOLPIX P80 (1536 2048) – Nikon E7600 (1536 2048)  
 2 Nikon COOLPIX S200 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)  
 2 Nikon COOLPIX S210 (2448 3264) – Fujifilm FinePix F480 (2448 3264)  
 2 Nikon COOLPIX S4 (2112 2816) – Nikon COOLPIX S10 (2112 2816)  
 2 Nikon COOLPIX S550 (2736 3648) – Olympus E-510 (2736 3648)  
 2 Nikon COOLPIX S700 (3000 4000) – Nikon COOLPIX P5100 (3000 4000)  
 2 Nikon D100 (2000 3008) – Nikon D40 (2000 3008)  
 2 Nikon D200 (685 1024) – Nikon D80 (685 1024)  
 2 Nikon D200 (803 1200) – Nikon D700 (803 1200)  
 2 Nikon D2X (2136 3216) – Nikon D300 (2136 3216)  
 2 Nikon D2X (2848 4288) – Nikon D300 (2848 4288)  
 2 Nikon D300 (1068 1600) – Pentax \*ist D (1068 1600)  
 2 Nikon D300 (1360 2048) – Nikon D90 (1360 2048)  
 2 Nikon D300 (1424 2144) – Nikon D90 (1424 2144)  
 2 Nikon D300 (2848 4288) – Nikon D90 (2848 4288)  
 2 Nikon D300 (531 800) – Canon EOS 5D (531 800)  
 2 Nikon D300 (679 1024) – Nikon D3 (679 1024)  
 2 Nikon D3 (2832 4256) – Nikon D700 (2832 4256)  
 2 Nikon D40 (1000 1504) – Nikon D50 (1000 1504)  
 2 Nikon D40 (1496 2256) – Nikon D50 (1496 2256)  
 2 Nikon D40 (2000 3008) – Nikon D50 (2000 3008)  
 2 Nikon D40 (2000 3008) – Nikon D70s (2000 3008)  
 2 Nikon D40 (426 640) – Canon EOS 400D DIGITAL (426 640)  
 2 Nikon D40 (532 800) – Canon EOS DIGITAL REBEL (532 800)  
 2 Nikon D40 (532 800) – Nikon D50 (532 800)  
 2 Nikon D40 (683 1024) – Nikon D300 (683 1024)  
 2 Nikon D40 (848 1280) – Nikon D50 (848 1280)  
 2 Nikon D40 (999 1512) – Nikon D70 (999 1512)  
 2 Nikon D40 (999 1512) – Nikon D70s (999 1512)  
 2 Nikon D40X (1944 2896) – Nikon D80 (1944 2896)  
 2 Nikon D40X (2592 3872) – Nikon D80 (2592 3872)  
 2 Nikon D40X (2600 3888) – Nikon D80 (2600 3888)  
 2 Nikon D40X (322 480) – Nikon D60 (322 480)  
 2 Nikon D40X (537 800) – Nikon D60 (537 800)  
 2 Nikon D50 (1057 1600) – Nikon D40 (1057 1600)  
 2 Nikon D50 (1496 2256) – Nikon D40 (1496 2256)  
 2 Nikon D50 (2000 3008) – Nikon D40 (2000 3008)  
 2 Nikon D50 (530 800) – Nikon D40 (530 800)  
 2 Nikon D60 (1296 1936) – Nikon D200 (1296 1936)  
 2 Nikon D60 (1296 1936) – Nikon D80 (1296 1936)

2 Nikon D60 (1944 2896) – Nikon D80 (1944 2896)  
 2 Nikon D60 (2592 3872) – Nikon D40X (2592 3872)  
 2 Nikon D60 (537 800) – Nikon D80 (537 800)  
 2 Nikon D700 (2832 4256) – Nikon D3 (2832 4256)  
 2 Nikon D70 (1488 2240) – Nikon D70s (1488 2240)  
 2 Nikon D70s (1488 2240) – Nikon D70 (1488 2240)  
 2 Nikon D80 (1296 1936) – Nikon D40X (1296 1936)  
 2 Nikon D80 (1296 1936) – Pentax K10D (1296 1936)  
 2 Nikon D80 (1371 2048) – Nikon D40X (1371 2048)  
 2 Nikon D80 (1944 2896) – Nikon D200 (1944 2896)  
 2 Nikon D80 (1944 2896) – Nikon D60 (1944 2896)  
 2 Nikon D80 (2592 3872) – Nikon D40X (2592 3872)  
 2 Nikon D80 (2600 3888) – Nikon D40X (2600 3888)  
 2 Nikon D80 (686 1024) – Pentax K10D (686 1024)  
 2 Nikon D80 (859 1280) – Nikon D40X (859 1280)  
 2 Nikon D90 (1360 2048) – Nikon D300 (1360 2048)  
 2 Nikon D90 (2136 3216) – Nikon D300 (2136 3216)  
 2 Nikon D90 (2848 4288) – Nikon D300 (2848 4288)  
 2 Nikon D90 (425 640) – Nikon D300 (425 640)  
 2 Nikon E2100 (1200 1600) – Konica Minolta DiMAGE X50 (1200 1600)  
 2 Nikon E3200 (1536 2048) – Nikon E885 (1536 2048)  
 2 Nikon E3200 (1536 2048) – Nikon E995 (1536 2048)  
 2 Nikon E4300 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272)  
 2 Nikon E4500 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272)  
 2 Nikon E4800 (1712 2288) – Nikon E4600 (1712 2288)  
 2 Nikon E5200 (1944 2592) – LG Electronics KU990 (1944 2592)  
 2 Nikon E5200 (1944 2592) – Nikon COOLPIX P4 (1944 2592)  
 2 Nikon E5700 (1920 2560) – Olympus C5050Z (1920 2560)  
 2 Nikon E5700 (960 1280) – Panasonic DMC-FX8 (960 1280)  
 2 Nikon E7600 (768 1024) – Nikon COOLPIX L3 (768 1024)  
 2 Nikon E995 (480 640) – Sony DSC-W80 (480 640)  
 2 Olympus C180,D435 (480 640) – Olympus FE190/X750 (480 640)  
 2 Olympus C4100Z,C4000Z (1712 2288) – Nikon E4600 (1712 2288)  
 2 Olympus C4100Z,C4000Z (766 1024) – Olympus C765UZ (766 1024)  
 2 Olympus C5050Z (1920 2560) – Olympus D595Z,C500Z (1920 2560)  
 2 Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)  
 2 Olympus C770UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)  
 2 Olympus E-300 (2448 3264) – Olympus E-500 (2448 3264)  
 2 Olympus E-410 (2736 3648) – Olympus E-510 (2736 3648)  
 2 Olympus E-420 (2736 3648) – Olympus E-510 (2736 3648)  
 2 Olympus E-420 (2736 3648) – Olympus E-520 (2736 3648)  
 2 Olympus E-500 (1224 1632) – Canon PowerShot SD870 IS (1224 1632)  
 2 Olympus E-500 (2448 3264) – Olympus E-300 (2448 3264)  
 2 Olympus E-500 (2448 3264) – Olympus u850SW,S850SW (2448 3264)  
 2 Olympus E-500 (2448 3264) – Sony DSC-N1 (2448 3264)  
 2 Olympus E-510 (2736 3648) – Casio EX-Z1000 (2736 3648)  
 2 Olympus E-510 (2736 3648) – Olympus E-410 (2736 3648)  
 2 Olympus E-510 (2736 3648) – Olympus E-420 (2736 3648)  
 2 Olympus E-510 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648)  
 2 Olympus E-510 (2736 3648) – Panasonic DMC-FX35 (2736 3648)  
 2 Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix Z100fd (2448 3264)  
 2 Olympus FE340,X855,C560 (2448 3264) – Nikon COOLPIX S210 (2448 3264)  
 2 Olympus u1010,S1010 (1920 2560) – Panasonic DMC-FZ20 (1920 2560)  
 2 Olympus u1030SW,S1030SW (1920 2560) – Olympus E-420 (1920 2560)  
 2 Olympus u1030SW,S1030SW (2736 3648) – Olympus E-510 (2736 3648)  
 2 Olympus u10D,S300D,u300D (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
 2 Olympus u1200,S1200 (3000 4000) – Nikon COOLPIX P5100 (3000 4000)  
 2 Olympus u30D,S410D,u410D (1536 2048) – Olympus u725SW,S725SW (1536 2048)  
 2 Olympus u30D,S410D,u410D (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
 2 Olympus u710,S710 (2304 3072) – Olympus u740,S740 (2304 3072)  
 2 Olympus u710,S710 (2304 3072) – Olympus u770SW,S770SW (2304 3072)  
 2 Olympus u710,S710 (2304 3072) – Olympus u790SW,S790SW (2304 3072)  
 2 Olympus u725SW,S725SW (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
 2 Olympus u760,S760 (2304 3072) – Olympus u710,S710 (2304 3072)  
 2 Olympus u770SW,S770SW (1536 2048) – Olympus u10D,S300D,u300D (1536 2048)  
 2 Olympus u770SW,S770SW (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
 2 Olympus u770SW,S770SW (2304 3072) – Olympus u710,S710 (2304 3072)  
 2 Olympus u770SW,S770SW (2304 3072) – Olympus u790SW,S790SW (2304 3072)  
 2 Olympus u790SW,S790SW (2304 3072) – Olympus u770SW,S770SW (2304 3072)  
 2 Olympus u790SW,S790SW (336 448) – Panasonic DMC-FZ7 (336 448)  
 2 Olympus u820,S820 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264)  
 2 Olympus u830,S830 (2448 3264) – Olympus u850SW,S850SW (2448 3264)  
 2 Olympus u850SW,S850SW (1536 2048) – Olympus u770SW,S770SW (1536 2048)  
 2 Olympus u850SW,S850SW (2448 3264) – Olympus E-500 (2448 3264)  
 2 Olympus uD600,S600 (2112 2816) – Olympus X-3,C-60Z (2112 2816)  
 2 Olympus uD800,S800 (1536 2048) – Olympus u740,S740 (1536 2048)  
 2 Olympus uD800,S800 (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
 2 Olympus u-miniS,StylusVS (1920 2560) – Olympus u40D,S500,uD500 (1920 2560)  
 2 Olympus X100,D540Z,C310Z (1200 1600) – Fujifilm FinePix F480 (1200 1600)  
 2 Olympus X-3,C-60Z (2112 2816) – Olympus uD600,S600 (2112 2816)  
 2 Olympus X400,D580Z,C460Z (1197 1600) – Olympus C765UZ (1197 1600)  
 2 Olympus X400,D580Z,C460Z (598 800) – Nikon E4600 (598 800)  
 2 Panasonic DMC-FS3 (1200 1600) – Canon DIGITAL IXUS 75 (1200 1600)  
 2 Panasonic DMC-FS3 (2448 3264) – Panasonic DMC-TZ4 (2448 3264)  
 2 Panasonic DMC-FX07 (1080 1920) – Panasonic DMC-LX2 (1080 1920)  
 2 Panasonic DMC-FX07 (1200 1600) – Panasonic DMC-TZ3 (1200 1600)  
 2 Panasonic DMC-FX07 (2304 3072) – Panasonic DMC-TZ3 (2304 3072)  
 2 Panasonic DMC-FX10 (2112 2816) – Panasonic DMC-FZ7 (2112 2816)  
 2 Panasonic DMC-FX12 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)  
 2 Panasonic DMC-FX30 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)  
 2 Panasonic DMC-FX30 (450 600) – Panasonic DMC-TZ11 (450 600)  
 2 Panasonic DMC-FX3 (1536 2048) – Panasonic DMC-TZ3 (1536 2048)  
 2 Panasonic DMC-FX3 (2112 2816) – Panasonic DMC-FX01 (2112 2816)  
 2 Panasonic DMC-FX35 (1920 2560) – Panasonic DMC-FX30 (1920 2560)  
 2 Panasonic DMC-FX35 (1920 2560) – Panasonic DMC-FZ8 (1920 2560)  
 2 Panasonic DMC-FX7 (960 1280) – Panasonic DMC-FZ5 (960 1280)  
 2 Panasonic DMC-FX9 (2112 2816) – Panasonic DMC-FX01 (2112 2816)

2 Panasonic DMC-FZ18 (1536 2048) – Panasonic DMC-LZ2 (1536 2048)  
 2 Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
 2 Panasonic DMC-FZ18 (2448 3264) – Panasonic DMC-FX100 (2448 3264)  
 2 Panasonic DMC-FZ20 (1920 2560) – Panasonic DMC-FZ5 (1920 2560)  
 2 Panasonic DMC-FZ4 (1728 2304) – Panasonic DMC-FZ10 (1728 2304)  
 2 Panasonic DMC-FZ50 (2448 3264) – Panasonic DMC-FZ18 (2448 3264)  
 2 Panasonic DMC-FZ5 (1200 1600) – Panasonic DMC-FX7 (1200 1600)  
 2 Panasonic DMC-FZ5 (1920 2560) – Panasonic DMC-FZ20 (1920 2560)  
 2 Panasonic DMC-FZ8 (1920 2560) – Panasonic DMC-FZ30 (1920 2560)  
 2 Panasonic DMC-FZ8 (2304 3072) – Panasonic DMC-LZ7 (2304 3072)  
 2 Panasonic DMC-LS60 (1536 2048) – Panasonic DMC-LZ7 (1536 2048)  
 2 Panasonic DMC-LS60 (2112 2816) – Panasonic DMC-FX10 (2112 2816)  
 2 Panasonic DMC-LS75 (2304 3072) – Panasonic DMC-LZ7 (2304 3072)  
 2 Panasonic DMC-LX2 (2160 3840) – Leica D-LUX 3 (2160 3840)  
 2 Panasonic DMC-LX2 (2376 4224) – Leica D-LUX 3 (2376 4224)  
 2 Panasonic DMC-LX2 (450 800) – Leica D-LUX 3 (450 800)  
 2 Panasonic DMC-LX2 (720 1280) – Panasonic DMC-TZ3 (720 1280)  
 2 Panasonic DMC-LX3 (2736 3648) – Panasonic DMC-FZ28 (2736 3648)  
 2 Panasonic DMC-LZ3 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
 2 Panasonic DMC-LZ7 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)  
 2 Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-FX07 (1920 2560)  
 2 Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-FZ18 (1920 2560)  
 2 Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-TZ3 (1920 2560)  
 2 Panasonic DMC-TZ1 (450 600) – Nikon E775 (450 600)  
 2 Panasonic DMC-TZ15 (2592 3456) – Panasonic DMC-TZ5 (2592 3456)  
 2 Panasonic DMC-TZ3 (600 800) – Panasonic DMC-LS3 (600 800)  
 2 Panasonic DMC-TZ4 (1840 3264) – Panasonic DMC-FX55 (1840 3264)  
 2 Panasonic DMC-TZ4 (2448 3264) – Panasonic DMC-FZ30 (2448 3264)  
 2 Panasonic DMC-TZ5 (1536 2048) – Panasonic DMC-LZ8 (1536 2048)  
 2 Panasonic DMC-TZ5 (1575 2800) – Canon PowerShot TX1 (1575 2800)  
 2 Panasonic DMC-TZ5 (768 1024) – Olympus E-510 (768 1024)  
 2 Pentax \*ist DL (1600 2400) – Pentax K100D (1600 2400)  
 2 Pentax \*ist DS (1024 1536) – Pentax K100D (1024 1536)  
 2 Pentax K10D (1296 1936) – Nikon D40X (1296 1936)  
 2 Pentax K10D (2000 3000) – Canon EOS DIGITAL REBEL XSi (2000 3000)  
 2 Pentax K20D (3104 4672) – Pentax Pentax K20D (3104 4672)  
 2 Pentax K20D (680 1024) – Nikon D300 (680 1024)  
 2 Pentax K20D (850 1280) – Canon EOS 40D (850 1280)  
 2 Pentax Optio A20 (2736 3648) – Pentax Optio A30 (2736 3648)  
 2 Pentax Optio M20 (768 1024) – Nikon COOLPIX L3 (768 1024)  
 2 Pentax Pentax K200D (2592 3872) – Pentax K200D (2592 3872)  
 2 Research In Motion BlackBerry 8120 (1200 1600) – Research In Motion BlackBerry 8110 (1200 1600)  
 2 Research In Motion BlackBerry 8320 (1200 1600) – Research In Motion BlackBerry 8310 (1200 1600)  
 2 Ricoh R8 (960 960) – Canon EOS 30D (960 960)  
 2 Samsung <KENOX S630 / S630> (2112 2816) – Nikon COOLPIX L1 (2112 2816)  
 2 Samsung NV20, VLUU NV20 (840 1120) – Samsung VLUU NV10, NV10 (840 1120)  
 2 Sanyo CG9 (2592 3456) – Sony DSC-H50 (2592 3456)  
 2 Sony CD MAVICA (1200 1600) – Sony CYBERSHOT (1200 1600)  
 2 Sony CYBERSHOT (1360 2048) – Canon EOS DIGITAL REBEL (1360 2048)  
 2 Sony CYBERSHOT (960 1280) – Sony DSC-P10 (960 1280)  
 2 Sony DSC-H1 (1728 2592) – Sony DSC-P100 (1728 2592)  
 2 Sony DSC-H7 (2176 3264) – Sony DSC-T200 (2176 3264)  
 2 Sony DSC-H9 (2448 3264) – Sony DSC-W90 (2448 3264)  
 2 Sony DSC-N1 (2448 3264) – Sony DSC-W100 (2448 3264)  
 2 Sony DSC-N2 (2432 3648) – Sony DSC-T300 (2432 3648)  
 2 Sony DSC-P10 (960 1280) – Sony CYBERSHOT (960 1280)  
 2 Sony DSC-P73 (1728 2304) – Sony DSC-P41 (1728 2304)  
 2 Sony DSC-P73 (1728 2304) – Sony DSC-S40 (1728 2304)  
 2 Sony DSC-P8 (1536 2048) – Sony DSC-P73 (1536 2048)  
 2 Sony DSC-S40 (1536 2304) – Sony DSC-S60 (1536 2304)  
 2 Sony DSC-S40 (1728 2304) – Sony DSC-P41 (1728 2304)  
 2 Sony DSC-S650 (2304 3072) – Sony DSC-S750 (2304 3072)  
 2 Sony DSC-S700 (2304 3072) – Sony DSC-S750 (2304 3072)  
 2 Sony DSC-S90 (1728 2304) – Sony DSC-S40 (1728 2304)  
 2 Sony DSC-T10 (1944 2592) – Sony MVC-CD500 (1944 2592)  
 2 Sony DSC-T200 (2176 3264) – Samsung Pro 815 (2176 3264)  
 2 Sony DSC-T50 (1224 1632) – Sony CYBERSHOT U (1224 1632)  
 2 Sony DSC-W35 (1224 1632) – Sony DSC-W55 (1224 1632)  
 2 Sony DSC-W35 (2048 3072) – Sony DSC-W55 (2048 3072)  
 2 Sony DSC-W35 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)  
 2 Sony DSC-W55 (2048 3072) – Sony DSC-W80 (2048 3072)  
 2 Sony DSC-W80 (2048 3072) – Fujifilm FinePix S5700 S700 (2048 3072)  
 2 Sony DSLR-A100 (2584 3864) – Sony DSLR-A200 (2584 3864)  
 2 Sony DSLR-A100 (2592 3872) – Nikon D80 (2592 3872)  
 2 Sony DSLR-A300 (300 448) – Sony DSLR-A100 (300 448)  
 2 Sony DSLR-A700 (2848 4272) – Canon EOS DIGITAL REBEL XSi (2848 4272)  
 2 Sony DSLR-A700 (533 800) – Canon EOS 450D (533 800)  
 2 Sony Ericsson K770i (1536 2048) – Sony ERICSSON Sony ERICSSON P1i (1536 2048)  
 2 Sony Ericsson K800i (1224 1632) – Samsung SPH-A800 (1224 1632)  
 2 Sony Ericsson W580i (480 640) – Sony Ericsson W660i (480 640)  
 2 Sony Ericsson W580i (480 640) – Sony Ericsson Z610i (480 640)  
 2 Sony FDMAVICA (1200 1600) – Sony CYBERSHOT (1200 1600)  
 2 Sony HDR-SR12E (2070 3680) – Sony HDR-SR11 (2070 3680)  
 2 SUPRA SLIMLINE X6 (403 537) – Supra DC 7900 (403 537)  
 2 V5VP (2400 3200) – V5V (2400 3200)  
 3 Canon EOS 10D (2040 3072) – Canon EOS 300D DIGITAL (2040 3072) – Canon EOS DIGITAL REBEL (2040 3072)  
 3 Canon EOS 10D (2048 3072) – Canon EOS 300D DIGITAL (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072)  
 3 Canon EOS-1D Mark III (2592 3888) – Canon EOS DIGITAL REBEL XSi (2592 3888) – Canon EOS 40D (2592 3888)  
 3 Canon EOS-1D Mark II N (2336 3504) – Canon EOS 20D (2336 3504) – Canon EOS 30D (2336 3504)  
 3 Canon EOS 20D (400 600) – Canon EOS 350D DIGITAL (400 600) – Canon EOS 400D DIGITAL (400 600)  
 3 Canon EOS 300D DIGITAL (2048 3072) – Canon PowerShot SD800 IS (2048 3072) – Fujifilm FinePix S5700 S700 (2048 3072)  
 3 Canon EOS 300D DIGITAL (2048 3072) – Fujifilm FinePix S5700 S700 (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072)  
 3 Canon EOS 350D DIGITAL (2304 3456) – Canon EOS 50D (2304 3456) – Canon EOS DIGITAL REBEL XT (2304 3456)  
 3 Canon EOS 400D DIGITAL (1296 1944) – Canon EOS 40D (1296 1944) – Canon EOS DIGITAL REBEL XTi (1296 1944)  
 3 Canon EOS 400D DIGITAL (2592 3888) – Canon EOS 40D (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)  
 3 Canon EOS 40D (1244 1867) – Canon EOS DIGITAL REBEL XT (1244 1867) – Canon EOS DIGITAL REBEL XTi (1244 1867)  
 3 Canon EOS 40D (1880 2816) – Canon EOS 400D DIGITAL (1880 2816) – Canon EOS DIGITAL REBEL XTi (1880 2816)

3 Canon EOS 40D (1880 2816) – Canon EOS DIGITAL REBEL XTi (1880 2816) – Fujifilm FinePix F650 (1880 2816)  
3 Canon EOS 40D (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)  
3 Canon EOS 40D (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888) – Canon EOS 400D DIGITAL (2592 3888)  
3 Canon EOS 40D (534 800) – Canon EOS DIGITAL REBEL XTi (534 800) – Canon EOS 400D DIGITAL (534 800)  
3 Canon EOS 450D (2848 4272) – Canon EOS Kiss X2 (2848 4272) – Canon EOS DIGITAL REBEL XSi (2848 4272)  
3 Canon EOS 5D (333 500) – Canon EOS 400D DIGITAL (333 500) – Canon EOS 40D (333 500)  
3 Canon EOS DIGITAL REBEL XT (1067 1600) – Canon EOS DIGITAL REBEL XTi (1067 1600) – Canon EOS 400D DIGITAL (1067 1600)  
3 Canon EOS DIGITAL REBEL XT (1866 2800) – Canon EOS DIGITAL REBEL XTi (1866 2800) – Canon EOS 400D DIGITAL (1866 2800)  
3 Canon EOS DIGITAL REBEL XT (532 800) – Nikon D40 (532 800) – Canon EOS 40D (532 800)  
3 Canon EOS DIGITAL REBEL XTi (1066 1600) – Canon EOS 40D (1066 1600) – Canon EOS 20D (1066 1600)  
3 Canon EOS DIGITAL REBEL XTi (1068 1600) – Canon EOS 40D (1068 1600) – Panasonic DMC-FZ7 (1068 1600)  
3 Canon EOS DIGITAL REBEL XTi (683 1024) – Canon EOS 350D DIGITAL (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024)  
3 Canon EOS Kiss Digital N (1664 2496) – Canon EOS 350D DIGITAL (1664 2496) – Canon EOS DIGITAL REBEL XT (1664 2496)  
3 Canon EOS Kiss Digital X (1068 1600) – Canon EOS DIGITAL REBEL XTi (1068 1600) – Canon EOS 40D (1068 1600)  
3 Canon EOS Kiss Digital X (1288 1936) – Canon EOS 400D DIGITAL (1288 1936) – Canon EOS DIGITAL REBEL XTi (1288 1936)  
3 Canon EOS Kiss Digital X (1880 2816) – Canon EOS 400D DIGITAL (1880 2816) – Canon EOS DIGITAL REBEL XTi (1880 2816)  
3 Canon EOS Kiss Digital X (2588 3888) – Canon EOS 400D DIGITAL (2588 3888) – Canon EOS DIGITAL REBEL XTi (2588 3888)  
3 Canon EOS Kiss Digital X (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)  
3 Canon EOS Kiss X2 (2848 4272) – Canon EOS 450D (2848 4272) – Canon EOS DIGITAL REBEL XSi (2848 4272)  
3 Canon IXY DIGITAL 900 IS (1152 1536) – Panasonic DMC-FX07 (1152 1536) – Canon PowerShot SD1000 (1152 1536)  
3 Canon PowerShot A620 (675 900) – Sony DSC-H5 (675 900) – Sony DSC-W70 (675 900)  
3 Canon PowerShot A640 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon PowerShot A610 (1200 1600)  
3 Canon PowerShot A650 IS (3000 4000) – Canon PowerShot G9 (3000 4000) – Sony DSC-W200 (3000 4000)  
3 Canon PowerShot A80 (1704 2272) – Canon DIGITAL IXUS 400 (1704 2272) – Canon PowerShot SD600 (1704 2272)  
3 Canon PowerShot A80 (1704 2272) – Canon EOS 350D DIGITAL (1664 2496) – Canon EOS DIGITAL REBEL XT (1664 2496)  
3 Canon PowerShot G9 (3000 4000) – Fujifilm FinePix F50fd (3000 4000) – Fujifilm FinePix F100fd (3000 4000)  
3 Canon PowerShot S3 IS (2112 2816) – Casio EX-S600 (2112 2816) – Sony DSC-W50 (2112 2816)  
3 Canon PowerShot SD1000 (758 1010) – Sony DSC-L1 (758 1010) – Nikon COOLPIX L14 (758 1010)  
3 Canon PowerShot SD300 (1704 2272) – Canon PowerShot A520 (1704 2272) – Canon PowerShot S3 IS (1704 2272)  
3 Canon PowerShot SD630 (1584 2816) – Canon PowerShot SD600 (1584 2816) – Canon PowerShot S3 IS (1584 2816)  
3 Canon PowerShot SD630 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Canon PowerShot A700 (2112 2816)  
3 Canon PowerShot SD750 (480 640) – Canon PowerShot A200 (480 640) – Canon PowerShot A560 (480 640)  
3 Canon PowerShot SD790 IS (2736 3648) – Canon PowerShot A1000 IS (2736 3648) – Canon PowerShot A640 (2736 3648)  
3 Canon PowerShot SD950 IS (3000 4000) – Canon DIGITAL IXUS 960 IS (3000 4000) – Canon PowerShot G9 (3000 4000)  
3 Casio EX-F1 (2112 2816) – Casio EX-V8 (2112 2816) – Casio EX-Z80 (2112 2816)  
3 Casio EX-S10 (2736 3648) – Casio EX-Z1080 (2736 3648) – Casio EX-Z1050 (2736 3648)  
3 Casio EX-V7 (480 640) – Casio EX-Z1050 (480 640) – Casio EX-Z77 (480 640)  
3 Casio EX-Z1000 (2736 3648) – Olympus E-410 (2736 3648) – Olympus E-510 (2736 3648)  
3 Casio EX-Z1050 (1920 2560) – Casio EX-Z1080 (1920 2560) – Casio EX-Z77 (1920 2560)  
3 Casio EX-Z1080 (1200 1600) – Casio EX-S10 (1200 1600) – Casio EX-Z1050 (1200 1600)  
3 Casio EX-Z1080 (2432 3648) – Casio EX-S10 (2432 3648) – Casio EX-Z1050 (2432 3648)  
3 Casio EX-Z110 (1728 2304) – Fujifilm FinePix A345 (1728 2304) – Panasonic DMC-FZ7 (1728 2304)  
3 Casio EX-Z77 (1200 1600) – Casio EX-S880 (1200 1600) – Casio EX-Z100 (1200 1600)  
3 Casio EX-Z77 (1920 2560) – Casio EX-Z1080 (1920 2560) – Casio EX-Z1050 (1920 2560)  
3 Casio EX-Z80 (2448 3264) – Casio EX-S880 (2448 3264) – Casio EX-V8 (2448 3264)  
3 Casio EX-Z8 (2448 3264) – Casio EX-Z80 (2448 3264) – Casio EX-S880 (2448 3264)  
3 Digital Camera D55MP (1920 2560) – Digital Camera Vivicam (1920 2560) – Hewlett-Packard HP Photosmart E317 (1920 2560)  
3 Fujifilm FinePix A800 (1535 2047) – Olympus E-330 (1535 2047) – Fujifilm FinePix A820 (1535 2047)  
3 Fujifilm FinePix F20 (2136 2848) – Fujifilm FinePix F30 (2136 2848) – Fujifilm FinePix F10 (2136 2848)  
3 Fujifilm FinePix F31fd (1536 2048) – Minolta DiMAGE Xt (1536 2048) – Canon PowerShot SD750 (1536 2048)  
3 Fujifilm FinePix F485 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Nikon COOLPIX S210 (2448 3264)  
3 Fujifilm FinePixS2Pro (428 640) – Canon EOS 30D (428 640) – Nikon D80 (428 640)  
3 Fujifilm FinePix S5000 (963 1280) – Hewlett-Packard PhotoSmart R927 (V01.00) (963 1280) – Hewlett-Packard PhotoSmart R717 (V01.00)d (963 1280)  
3 Fujifilm FinePix S5700 S700 (2048 3072) – Sony DSC-W35 (2048 3072) – Sony DSC-W80 (2048 3072)  
3 Fujifilm FinePix S5700 S700 (600 800) – Fujifilm FinePix S9600 (600 800) – Nikon COOLPIX S210 (600 800)  
3 Fujifilm FinePix S8100fd (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Nikon COOLPIX S550 (2736 3648)  
3 Hewlett-Packard hp 635 Digital Camera (1200 1600) – Olympus E-510 (1200 1600) – Sony CYBERSHOT (1200 1600)  
3 Hewlett-Packard Photosmart M415 (1952 2576) – Hewlett-Packard Photosmart M417 (1952 2576) – Hewlett-Packard Photosmart M517 (1952 2576)  
3 HTC S620 (1024 1280) – T-Mobile Dash T-Mobile Dash (1024 1280) – Research In Motion BlackBerry 8100 Series (1024 1280)  
3 Kodak EASYSHARE V1073 DIGITAL CAMERA (2736 3648) – Kodak EASYSHARE Z1012 IS Digital Camera (2736 3648) – Kodak EASYSHARE M1033 DIGITAL CAMERA (2736 3648)  
3 Konica Minolta MAXXUM 5D (2000 3008) – Konica Minolta MAXXUM 5D (2000 3008) – Konica Minolta MAXXUM 7D (2000 3008)  
3 Konica Minolta MAXXUM 5D (2000 3008) – Konica Minolta MAXXUM 7D (2000 3008) – Konica Minolta DYNAX 5D (2000 3008)  
3 Minolta DiMAGE Z1 (960 1280) – Sony DSC-P10 (960 1280) – Sony DSC-H1 (960 1280)  
3 Nikon COOLPIX P5100 (3000 4000) – Olympus u1200,S1200 (3000 4000) – Sony DSC-W200 (3000 4000)  
3 Nikon COOLPIX P80 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Nikon E7600 (1536 2048)  
3 Nikon COOLPIX S10 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S4 (2112 2816)  
3 Nikon COOLPIX S4 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Nikon COOLPIX L6 (2112 2816)  
3 Nikon COOLPIX S51 (490 653) – Canon PowerShot A630 (490 653) – Camera 8MP-9HX (490 653)  
3 Nikon COOLPIX S52 (2592 3456) – Panasonic DMC-TZ5 (2592 3456) – Sony DSC-H50 (2592 3456)  
3 Nikon COOLPIX S52 (2592 3456) – Sony DSC-H50 (2592 3456) – Panasonic DMC-TZ5 (2592 3456)  
3 Nikon D2X (2848 4288) – Nikon D300 (2848 4288) – Nikon D90 (2848 4288)  
3 Nikon D300 (1062 1600) – Nikon D90 (1062 1600) – Canon EOS 300D DIGITAL (1062 1600)  
3 Nikon D3 (677 1024) – Nikon D40 (677 1024) – Nikon D70s (677 1024)  
3 Nikon D40 (1361 2048) – Nikon D50 (1361 2048) – Nikon D70s (1361 2048)  
3 Nikon D40 (2000 3008) – Nikon D50 (2000 3008) – Nikon D70s (2000 3008)  
3 Nikon D40 (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008)  
3 Nikon D40X (1944 2896) – Nikon D60 (1944 2896) – Nikon D80 (1944 2896)  
3 Nikon D40X (1944 2896) – Nikon D80 (1944 2896) – Nikon D60 (1944 2896)  
3 Nikon D40X (2592 3872) – Nikon D60 (2592 3872) – Nikon D80 (2592 3872)  
3 Nikon D40X (2592 3872) – Nikon D80 (2592 3872) – Nikon D200 (2592 3872)  
3 Nikon D40X (2592 3872) – Nikon D80 (2592 3872) – Sony DSLR-A100 (2592 3872)  
3 Nikon D40X (2592 3872) – Pentax K10D (2592 3872) – Nikon D80 (2592 3872)  
3 Nikon D40X (857 1280) – Nikon D200 (857 1280) – Nikon D80 (857 1280)  
3 Nikon D40X (859 1280) – Nikon D200 (859 1280) – Nikon D80 (859 1280)  
3 Nikon D50 (1000 1504) – Nikon D70s (1000 1504) – Nikon D40 (1000 1504)  
3 Nikon D50 (2000 3008) – Nikon D70 (2000 3008) – Nikon D40 (2000 3008)  
3 Nikon D50 (2000 3008) – Nikon D70s (2000 3008) – Nikon D40 (2000 3008)  
3 Nikon D60 (1944 2896) – Nikon D40X (1944 2896) – Nikon D80 (1944 2896)  
3 Nikon D60 (1944 2896) – Nikon D80 (1944 2896) – Nikon D40X (1944 2896)  
3 Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872)  
3 Nikon D60 (2592 3872) – Nikon D80 (2592 3872) – Nikon D40X (2592 3872)  
3 Nikon D70 (1998 3024) – Nikon D40 (1998 3024) – Nikon D50 (1998 3024)  
3 Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)  
3 Nikon D70s (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)  
3 Nikon D80 (2592 3872) – Nikon D40X (2592 3872) – Pentax K200D (2592 3872)  
3 Nikon D80 (537 800) – Nikon D40X (537 800) – Nikon D60 (537 800)

3 Nikon E2100 (1200 1600) – Olympus C200Z,D510Z (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600)  
3 Nikon E4300 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Nikon E4500 (1704 2272)  
3 Nikon E4300 (1704 2272) – Nikon E4500 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272)  
3 Nikon E4600 (1712 2288) – Olympus C4100Z,C4000Z (1712 2288) – Olympus C770UZ (1712 2288)  
3 Nikon E7600 (768 1024) – Pentax Optio M20 (768 1024) – Nikon COOLPIX L3 (768 1024)  
3 Olympus C5050Z (1920 2560) – Panasonic DMC-FZ20 (1920 2560) – Pentax Optio S5z (1920 2560)  
3 Olympus C750UZ (1712 2288) – Olympus C770UZ (1712 2288) – Nikon E4600 (1712 2288)  
3 Olympus C765UZ (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)  
3 Olympus C765UZ (1712 2288) – Olympus C770UZ (1712 2288) – Nikon E4600 (1712 2288)  
3 Olympus C765UZ (1712 2288) – Olympus C770UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)  
3 Olympus C770UZ (1712 2288) – Nikon E4600 (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)  
3 Olympus C8080WZ (2448 3264) – Sony DSC-T100 (2448 3264) – Sony DSC-H9 (2448 3264)  
3 Olympus D555Z,C315Z (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Nikon COOLPIX L3 (1944 2592)  
3 Olympus D595Z,C500Z (1920 2560) – Nikon E5700 (1920 2560) – Olympus C5050Z (1920 2560)  
3 Olympus D595Z,C500Z (1920 2560) – Olympus C5050Z (1920 2560) – Konica Minolta DiMAGE Z5 (1920 2560)  
3 Olympus E-300 (2448 3264) – Olympus E-500 (2448 3264) – Olympus u850SW,S850SW (2448 3264)  
3 Olympus E-300 (2448 3264) – Olympus u850SW,S850SW (2448 3264) – Olympus E-500 (2448 3264)  
3 Olympus E-3 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648)  
3 Olympus E-410 (2736 3648) – Olympus E-400 (2736 3648) – Olympus E-510 (2736 3648)  
3 Olympus E-410 (2736 3648) – Olympus E-420 (2736 3648) – Olympus E-510 (2736 3648)  
3 Olympus E-410 (2736 3648) – Olympus E-510 (2736 3648) – Olympus u1010,S1010 (2736 3648)  
3 Olympus E-410 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648) – Olympus E-510 (2736 3648)  
3 Olympus E-510 (2736 3648) – Olympus E-3 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648)  
3 Olympus FE190/X750 (2112 2816) – Olympus SP500UZ (2112 2816) – Olympus FE-120,X-700 (2112 2816)  
3 Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Fujifilm FinePix Z1000fd (2448 3264)  
3 Olympus u1010,S1010 (2736 3648) – Olympus E-520 (2736 3648) – Olympus E-400 (2736 3648)  
3 Olympus u30D,S410D,u410D (1536 2048) – Olympus u725SW,S725SW (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
3 Olympus u725SW,S725SW (2304 3072) – Olympus u720SW,S720SW (2304 3072) – Olympus u770SW,S770SW (2304 3072)  
3 Olympus u760,S760 (2304 3072) – Olympus u720SW,S720SW (2304 3072) – Olympus u770SW,S770SW (2304 3072)  
3 Olympus u770SW,S770SW (1536 2048) – Olympus u725SW,S725SW (1536 2048) – Olympus u850SW,S850SW (1536 2048)  
3 Olympus u790SW,S790SW (2304 3072) – Olympus u740,S740 (2304 3072) – Olympus u710,S710 (2304 3072)  
3 Olympus u795SW,S795SW (2304 3072) – Olympus u790SW,S790SW (2304 3072) – Olympus u770SW,S770SW (2304 3072)  
3 Olympus X100,D540Z,C310Z (1536 2048) – Nikon E3100 (1536 2048) – Nikon E7600 (1536 2048)  
3 Panasonic DMC-FS5 (2736 3648) – Panasonic DMC-FX35 (2736 3648) – Panasonic DMC-FX36 (2736 3648)  
3 Panasonic DMC-FX07 (1920 2560) – Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
3 Panasonic DMC-FX12 (2304 3072) – Panasonic DMC-FX30 (2304 3072) – Panasonic DMC-LZ7 (2304 3072)  
3 Panasonic DMC-FX50 (1728 3072) – Panasonic DMC-FX07 (1728 3072) – Panasonic DMC-LX2 (1728 3072)  
3 Panasonic DMC-FX50 (2304 3072) – Panasonic DMC-FX07 (2304 3072) – Panasonic DMC-TZ3 (2304 3072)  
3 Panasonic DMC-FX7 (1920 2560) – Panasonic DMC-FZ5 (1920 2560) – Panasonic DMC-FZ20 (1920 2560)  
3 Panasonic DMC-FX8 (1920 2560) – Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
3 Panasonic DMC-FX9 (2112 2816) – Panasonic DMC-TZ2 (2112 2816) – Panasonic DMC-FX01 (2112 2816)  
3 Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-TZ3 (1920 2560)  
3 Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ3 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
3 Panasonic DMC-FX7 (1920 2560) – Samsung <KENOX S1050 / S1050> (2736 3648) – Casio EX-Z1050 (2736 3648)  
3 Panasonic DMC-LS70 (480 640) – Sony DSC-W5 (480 640) – Canon PowerShot SD1100 IS (480 640)  
3 Panasonic DMC-LX2 (900 1600) – Canon PowerShot A550 (900 1600) – Canon PowerShot SD1000 (900 1600)  
3 Panasonic DMC-LZ8 (2448 3264) – Panasonic DMC-FS3 (2448 3264) – Panasonic DMC-TZ4 (2448 3264)  
3 Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-FX07 (1920 2560) – Panasonic DMC-FZ18 (1920 2560)  
3 Panasonic DMC-TZ3 (1920 2560) – Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)  
3 Pentax \*ist DS (2000 3008) – Nikon D40 (2000 3008) – Pentax K10D (2000 3008)  
3 Pentax K100D Super (2000 3008) – Pentax K100D (2000 3008) – Pentax \*ist DS (2000 3008)  
3 Pentax K10D (1071 1600) – Nikon D80 (1071 1600) – Nikon D40X (1071 1600)  
3 Pentax Optio A20 (2736 3648) – Pentax Optio A30 (2736 3648) – Pentax Optio S10 (2736 3648)  
3 Pentax Optio M40 (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Fujifilm FinePix Z1000fd (2448 3264)  
3 Research In Motion BlackBerry 8130 (248 336) – Research In Motion BlackBerry 8310 (248 336) – Research In Motion BlackBerry 8330 (248 336)  
3 Research In Motion BlackBerry 8320 (480 640) – Research In Motion BlackBerry 8330 (480 640) – Research In Motion BlackBerry 8310 (480 640)  
3 Research In Motion BlackBerry 8320 (600 800) – Research In Motion BlackBerry 8310 (600 800) – Research In Motion BlackBerry 8330 (600 800)  
3 Ricoh GX200 (3000 4000) – Kodak V1253 ZOOM DIGITAL CAMERA (3000 4000) – Canon PowerShot G9 (3000 4000)  
3 Samsung VLUU NV10, NV10 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Nikon COOLPIX S550 (2736 3648)  
3 Sony CYBERSHOT (1200 1600) – Konica Minolta DiMAGE Z10 (1200 1600) – Konica Minolta DiMAGE X50 (1200 1600)  
3 Sony DCR-DVD505 (1134 2016) – Sony DCR-HC90 (1134 2016) – Sony HDR-SR1 (1134 2016)  
3 Sony DSC-H2 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Sony DSC-W50 (2112 2816)  
3 Sony DSC-H3 (1080 1920) – Sony DSC-W90 (1080 1920) – Sony DSC-T200 (1080 1920)  
3 Sony DSC-P10 (1944 2592) – Sony DSC-V1 (1944 2592) – Sony DSC-P92 (1944 2592)  
3 Sony DSC-P32 (480 640) – Sony DSC-P72 (480 640) – Sony CYBERSHOT (480 640)  
3 Sony DSC-P32 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P10 (960 1280)  
3 Sony DSC-P73 (480 640) – Sony CYBERSHOT (480 640) – Sony DSC-T1 (480 640)  
3 Sony DSC-P8 (1536 2048) – Sony DSC-P10 (1536 2048) – Sony CYBERSHOT (1536 2048)  
3 Sony DSC-P92 (360 480) – Sony DSC-P200 (360 480) – Panasonic DMC-TZ1 (360 480)  
3 Sony DSC-S40 (1536 2048) – Sony DSC-S600 (1536 2048) – Sony DSC-W5 (1536 2048)  
3 Sony DSC-S600 (1872 2816) – Sony DSC-W50 (1872 2816) – Sony DSC-T9 (1872 2816)  
3 Sony DSC-S700 (2304 3072) – Olympus FE210,X775 (2304 3072) – Sony DSC-S750 (2304 3072)  
3 Sony DSC-S750 (800 1067) – Sony DSC-W50 (800 1067) – Olympus FE250/X800 (800 1067)  
3 Sony DSC-T10 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)  
3 Sony DSC-T200 (2176 3264) – Sony DSC-H9 (2176 3264) – Sony DSC-H7 (2176 3264)  
3 Sony DSC-W150 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-N1 (2448 3264)  
3 Sony DSC-W30 (2112 2816) – Sony DSC-W50 (2112 2816) – Sony DSC-H2 (2112 2816)  
3 Sony DSC-W35 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Sony DSC-W80 (2304 3072)  
3 Sony DSC-W55 (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072) – Sony DSC-S750 (2048 3072)  
3 Sony DSC-W55 (336 448) – Panasonic DMC-LX2 (336 448) – Casio EX-Z75 (336 448)  
3 Sony DSC-W55 (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL (533 800)  
3 Sony DSLR-A100 (2592 3872) – Sony DSLR-A200 (2592 3872) – Sony DSLR-A300 (2592 3872)  
3 Sony DSLR-A100 (536 800) – Nikon D80 (536 800) – Nikon D40X (536 800)  
3 Sony DSLR-A100 (685 1024) – Nikon D80 (685 1024) – Nikon D200 (685 1024)  
3 Sony DSLR-A200 (1936 2896) – Sony DSLR-A100 (1936 2896) – Sony DSLR-A300 (1936 2896)  
3 Sony DSLR-A300 (2592 3872) – Sony DSLR-A200 (2592 3872) – Sony DSLR-A100 (2592 3872)  
3 Sony DSLR-A350 (681 1024) – Nikon D40 (681 1024) – Nikon D100 (681 1024)  
3 Sony DSLR-A700 (2840 4272) – Canon EOS 450D (2840 4272) – Canon EOS DIGITAL REBEL XSi (2840 4272)  
3 Sony Ericsson K800i (1224 1632) – Panasonic DMC-FZ18 (1224 1632) – Canon DC20 (1224 1632)  
3 Sony Ericsson K800i (1536 2048) – Sony Ericsson K810i (1536 2048) – Nikon COOLPIX P5100 (1536 2048)  
3 Sony MVC-CD500 (480 640) – Sony FDMAVICA (480 640) – Sony CYBERSHOT (480 640)  
4 CAMERA 5MP-9EY (1920 2560) – Minolta DiMAGE F300 (1920 2560) – Vivitar ViviCam5355 (1920 2560) – Nikon E5700 (1920 2560)  
4 Canon DIGITAL IXUS 960 IS (3000 4000) – Canon PowerShot SD950 IS (3000 4000) – Canon PowerShot A650 IS (3000 4000) – Canon PowerShot G9 (3000 4000)  
4 Canon EOS 1000D (2592 3888) – Canon EOS-1D Mark III (2592 3888) – Canon EOS DIGITAL REBEL XS (2592 3888) – Canon EOS 40D (2592 3888)  
4 Canon EOS 10D (1360 2048) – Sony CYBERSHOT (1360 2048) – Canon EOS 300D DIGITAL (1360 2048) – Canon EOS DIGITAL REBEL (1360 2048)  
4 Canon EOS-1D Mark III (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS 40D (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)  
4 Canon EOS 20D (1152 1728) – Canon EOS 350D DIGITAL (1152 1728) – Canon EOS 30D (1152 1728) – Canon EOS DIGITAL REBEL XT (1152 1728)

4 Canon EOS 30D (1067 1600) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (1067 1600) – Canon EOS 400D DIGITAL (1067 1600) – Canon EOS DIGITAL REBEL XT (1067 1600)

4 Canon EOS 30D (1152 1728) – Canon EOS 350D DIGITAL (1152 1728) – Canon EOS 20D (1152 1728) – Canon EOS DIGITAL REBEL XT (1152 1728)

4 Canon EOS 350D (2304 3456) – Canon EOS Kiss Digital N (2304 3456) – Canon EOS 350D DIGITAL (2304 3456) – Canon EOS DIGITAL REBEL XT (2304 3456)

4 Canon EOS 400D DIGITAL (2592 3888) – Canon EOS 40D (2592 3888) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (2592 3888) – Canon EOS DIGITAL REBEL XS (2592 3888)

4 Canon EOS 40D (2592 3888) – Canon EOS-1D Mark III (2592 3888) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (2592 3888) – Sony DSC-R1 (2592 3888)

4 Canon EOS 40D (2592 3888) – Sony DSC-R1 (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XT (2592 3888)

4 Canon EOS 40D (600 900) – Canon EOS 5D (425 640) – Canon EOS 30D (425 640) – Canon EOS-1D Mark III (425 640)

4 Canon EOS 40D (600 900) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (600 900) – Canon EOS 30D DIGITAL (600 900) – Canon EOS DIGITAL REBEL XT (600 900)

4 Canon EOS 40D (682 1024) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (682 1024) – Nikon D50 (682 1024) – Canon EOS 5D (682 1024)

4 Canon EOS D60 (2048 3072) – Canon EOS 10D (2048 3072) – Canon EOS 300D DIGITAL (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072)

4 Canon EOS DIGITAL REBEL (1365 2048) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (1365 2048) – Canon EOS 40D (1365 2048) – Canon EOS DIGITAL REBEL XT (1365 2048)

4 Canon EOS DIGITAL REBEL (850 1280) – Olympus C765UZ (850 1280) – Nikon D90 (850 1280) – Nikon D300 (850 1280)

4 Canon EOS DIGITAL REBEL XT<sub>i</sub> (683 1024) – Fujifilm FinePix S5700 S700 (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024) – Canon EOS 450D (683 1024)

4 Canon PowerShot A520 (768 1024) – Canon PowerShot A70 (768 1024) – Canon PowerShot S400 (768 1024) – Canon PowerShot A20 (768 1024)

4 Canon PowerShot A570 IS (1728 3072) – Canon DIGITAL IXUS 75 (1728 3072) – Canon PowerShot SD1000 (1728 3072) – Canon PowerShot SD800 IS (1728 3072)

4 Canon PowerShot A70 (768 1024) – Canon PowerShot SD300 (768 1024) – Canon DC220 (768 1024) – Canon PowerShot S410 (768 1024)

4 Canon PowerShot A710 IS (1400 1867) – Canon PowerShot SD1000 (1400 1867) – Canon PowerShot S3 IS (1400 1867) – Canon PowerShot G7 (1400 1867)

4 Canon PowerShot G7 (2736 3648) – Ricoh GR DIGITAL 2 (2736 3648) – Olympus E-510 (2736 3648) – Olympus E-3 (2736 3648)

4 Canon PowerShot G9 (768 1024) – Samsung NV11, VLUU NV11 (768 1024) – Sony DSC-S650 (768 1024) – Sony DSC-T300 (768 1024)

4 Canon PowerShot SD400 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Fujifilm FinePix Z1 (1944 2592) – Pentax Optio 555 (1944 2592)

4 Canon PowerShot SD600 (1704 2272) – Nikon E4300 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Nikon E4500 (1704 2272)

4 Canon PowerShot SD700 IS (1584 2816) – Canon PowerShot SD600 (1584 2816) – Canon PowerShot S3 IS (1584 2816) – Canon PowerShot A540 (1584 2816)

4 Canon PowerShot SX100 IS (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Canon PowerShot A610 (1944 2592) – Canon PowerShot SD750 (1944 2592)

4 Canon PowerShot SX100 IS (768 1024) – Canon DIGITAL IXUS i (768 1024) – Canon PowerShot SD750 (768 1024) – Canon PowerShot SD550 (768 1024)

4 Casio EX-Z100 (1728 2304) – Casio EX-Z80 (1728 2304) – Casio EX-S880 (1728 2304) – Casio EX-S10 (1728 2304)

4 Casio EX-Z100 (2736 3648) – Casio EX-Z1080 (2736 3648) – Casio EX-S10 (2736 3648) – Casio EX-Z1050 (2736 3648)

4 Casio EX-Z200 (2304 3072) – Casio EX-Z12 (2304 3072) – Casio EX-V7 (2304 3072) – Casio EX-Z77 (2304 3072)

4 Casio EX-Z77 (576 768) – Canon IXY DIGITAL 80 (576 768) – Panasonic DMC-TZ2 (576 768) – Canon PowerShot SD750 (576 768)

4 Fujifilm FinePix F20 (2136 2848) – Fujifilm FinePix S6000fd (2136 2848) – Fujifilm FinePix S6500fd (2136 2848) – Fujifilm FinePix F30 (2136 2848)

4 Fujifilm FinePix F460 (480 640) – Sony DSC-P72 (480 640) – Sony DSC-W80 (480 640) – Canon PowerShot A590 IS (480 640)

4 Fujifilm FinePix S5700 S700 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-W80 (2304 3072)

4 Nikon COOLPIX L11 (2112 2816) – Sony DSC-S500 (2112 2816) – Casio EX-Z60 (2112 2816) – Nikon COOLPIX S3 (2112 2816)

4 Nikon COOLPIX L18 (1944 2592) – Nikon COOLPIX L5 (1944 2592) – Nikon E5200 (1944 2592) – Nikon COOLPIX P4 (1944 2592)

4 Nikon COOLPIX L4 (1704 2272) – Olympus FE100,X710 (1704 2272) – Canon PowerShot S3 IS (1704 2272) – Canon PowerShot A520 (1704 2272)

4 Nikon COOLPIX P80 (1536 2048) – Olympus C740UZ (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Nikon E7600 (1536 2048)

4 Nikon COOLPIX S200 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Sony DSC-W80 (2304 3072)

4 Nikon COOLPIX S200 (768 1024) – Pentax Optio M20 (768 1024) – Nikon E7600 (768 1024) – Nikon COOLPIX L3 (768 1024)

4 Nikon D100 (1063 1600) – Nikon D40 (1063 1600) – Nikon D70 (1063 1600) – Nikon D50 (1063 1600)

4 Nikon D200 (1944 2896) – Nikon D40X (1944 2896) – Nikon D80 (1944 2896) – Nikon D60 (1944 2896)

4 Nikon D200 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872) – Nikon D60 (2592 3872)

4 Nikon D200 (2592 3872) – Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872)

4 Nikon D200 (2592 3872) – Nikon D60 (2592 3872) – Nikon D80 (2592 3872) – Nikon D40X (2592 3872)

4 Nikon D2X (2848 4288) – Nikon D2Xs (2848 4288) – Nikon D90 (2848 4288) – Nikon D300 (2848 4288)

4 Nikon D50 (1064 1600) – Nikon D40 (1064 1600) – Pentax \*ist DS (1064 1600) – Nikon D70 (1064 1600)

4 Nikon D50 (426 640) – Nikon D70s (426 640) – Canon EOS 350D DIGITAL (426 640) – Nikon D40 (426 640)

4 Nikon D50 (851 1280) – Canon EOS 20D (851 1280) – Canon EOS DIGITAL REBEL XT<sub>i</sub> (851 1280) – Nikon D40 (851 1280)

4 Nikon D60 (2592 3872) – Nikon D200 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872)

4 Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D200 (2592 3872) – Nikon D80 (2592 3872)

4 Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872) – Nikon D200 (2592 3872)

4 Nikon D70 (2000 3008) – Nikon D70s (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)

4 Nikon D70s (1998 3024) – Nikon D70 (1998 3024) – Nikon D50 (1998 3024) – Nikon D40 (1998 3024)

4 Nikon D70s (2000 3008) – Nikon D40 (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008)

4 Nikon D70s (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)

4 Nikon D70s (2000 3008) – Pentax K100D (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)

4 Nikon D80 (2592 3872) – Pentax K200D (2592 3872) – Nikon D40X (2592 3872) – Nikon D200 (2592 3872)

4 Nikon E2200 (1200 1600) – Olympus C120,D380 (1200 1600) – Nikon E2100 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600)

4 Nikon E3200 (900 1200) – Panasonic DMC-FZ50 (900 1200) – Canon PowerShot A85 (900 1200) – Canon PowerShot A80 (900 1200)

4 Nikon E4100 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Nikon E2100 (1200 1600) – Olympus C700UZ (1200 1600)

4 Nikon E4500 (768 1024) – Samsung <KENOX S630 / Samsung S630> (768 1024) – Nikon E7600 (768 1024) – Nikon COOLPIX L3 (768 1024)

4 Nikon E4600 (1712 2288) – Olympus C765UZ (1712 2288) – Olympus C770UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)

4 Nikon E4800 (1712 2288) – Sanyo C40 (1712 2288) – Olympus C4100Z,C4000Z (1712 2288) – Nikon E4600 (1712 2288)

4 Olympus C170,D425 (1712 2288) – Nikon E4800 (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)

4 Olympus C3040Z (768 1024) – Pentax Optio M20 (768 1024) – Nikon E7600 (768 1024) – Nikon COOLPIX L3 (768 1024)

4 Olympus C4040Z (960 1280) – HTC HTC-Touch (960 1280) – Sony DSC-S40 (960 1280) – Olympus u-miniS,StylusVS (960 1280)

4 Olympus C765UZ (1712 2288) – Nikon E4600 (1712 2288) – Olympus C770UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)

4 Olympus C765UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288) – Nikon E4600 (1712 2288) – Olympus C770UZ (1712 2288)

4 Olympus E-300 (2448 3264) – Olympus u830,S830 (2448 3264) – Olympus E-500 (2448 3264) – Olympus u850SW,S850SW (2448 3264)

4 Olympus E-410 (2736 3648) – Olympus E-420 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648) – Olympus E-510 (2736 3648)

4 Olympus E-420 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Olympus E-510 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648)

4 Olympus E-500 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Nikon COOLPIX S210 (2448 3264)

4 Olympus FE340,X855,C560 (1920 2560) – Minolta DiMAGE F300 (1920 2560) – Olympus C5050Z (1920 2560) – Nikon E5700 (1920 2560)

4 Olympus SP550UZ (2304 3072) – Olympus FE240/X795 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Olympus FE230/X790 (2304 3072)

4 Olympus SP570UZ (1920 2560) – Nikon E5700 (1920 2560) – Sony CYBERSHOT (1920 2560) – Nikon E5000 (1920 2560)

4 Olympus u740,S740 (2304 3072) – Olympus u770SW,S770SW (2304 3072) – Olympus u790SW,S790SW (2304 3072) – Olympus u710,S710 (2304 3072)

4 Olympus u760,S760 (2304 3072) – Olympus u770SW,S770SW (2304 3072) – Olympus u790SW,S790SW (2304 3072) – Olympus u710,S710 (2304 3072)

4 Olympus u830,S830 (2448 3264) – Olympus u840,S840 (2448 3264) – Olympus E-500 (2448 3264) – Olympus u850SW,S850SW (2448 3264)

4 Panasonic DMC-FX30 (2304 3072) – Panasonic DMC-TZ5 (2304 3072) – Panasonic DMC-LZ7 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)

4 Panasonic DMC-FX500 (2736 3648) – Panasonic DMC-F55 (2736 3648) – Panasonic DMC-FX35 (2736 3648) – Panasonic DMC-FZ28 (2736 3648)

4 Panasonic DMC-FX55 (1536 2048) – Panasonic DMC-LZ6 (1536 2048) – Panasonic DMC-FX33 (1536 2048) – Panasonic DMC-LZ7 (1536 2048)

4 Panasonic DMC-FZ18 (450 600) – Sony DSC-S700 (450 600) – Canon PowerShot S400 (450 600) – Sony DSC-S500 (450 600)

4 Panasonic DMC-FZ8 (1920 2560) – Panasonic DMC-FX35 (1920 2560) – Panasonic DMC-TZ4 (1920 2560) – Panasonic DMC-FZ30 (1920 2560)

4 Pentax K100D Super (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008) – Nikon D70 (2000 3008)

4 Pentax Optio 33WR (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-T50 (1536 2048) – Sony DSC-W50 (1536 2048)

4 Pentax Optio M40 (2448 3264) – Olympus SP560UZ (2448 3264) – Fujifilm FinePix Z100fd (2448 3264) – Fujifilm FinePix S8000fd (2448 3264)

4 Pentax Optio Z10 (2448 3264) – Olympus SP560UZ (2448 3264) – Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix Z100fd (2448 3264)

4 Samsung ELECTRONICS SCD6040 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Nikon E4500 (1704 2272) – Nikon E4300 (1704 2272)

4 Samsung GX10 (2592 3872) – Nikon D80 (2592 3872) – Pentax K200D (2592 3872) – Pentax K10D (2592 3872)

4 Samsung NV15, VLUU NV15 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

4 Sony CD MAVICA (1704 2272) – Canon DIGITAL IXUS 430 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Samsung ELECTRONICS SCD6040 (1704 2272)

4 Sony DSC-H10 (2176 3264) – Sony DSC-H7 (2176 3264) – Sony DSC-W150 (2176 3264) – Sony DSC-T200 (2176 3264)

4 Sony DSC-H2 (1872 2816) – Sony DSC-S600 (1872 2816) – Sony DSC-T9 (1872 2816) – Sony DSC-W50 (1872 2816)

4 Sony DSC-H3 (1080 1920) – Sony DSC-T70 (1080 1920) – Sony DSC-W90 (1080 1920) – Sony DSC-W80 (1080 1920)

4 Sony DSC-H3 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-H9 (2448 3264)

4 Sony DSC-H3 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-W150 (2448 3264) – Sony DSC-H9 (2448 3264)

4 Sony DSC-L1 (1728 2304) – Sony DSC-S60 (1728 2304) – Sony DSC-S40 (1728 2304) – Sony DSC-S90 (1728 2304)

4 Sony DSC-P8 (1536 2048) – Sony DSC-P72 (1536 2048) – Sony DSC-P10 (1536 2048) – Sony CYBERSHOT (1536 2048)

4 Sony DSC-P8 (960 1280) – Sony DSC-P32 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P10 (960 1280)

4 Sony DSC-R1 (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888) – Canon EOS 40D (2592 3888)

4 Sony DSC-T100 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-W80 (1536 2048) – Nikon E885 (1536 2048)

4 Sony DSC-T200 (1080 1920) – Sony DSC-W100 (1080 1920) – Sony DSC-T50 (1080 1920) – Sony DSC-T70 (1080 1920)

4 Sony DSC-T200 (480 640) – Sony DSC-W80 (480 640) – Sony DSC-H3 (480 640) – Sony DCR-HC32E (480 640)

4 Sony DSC-W100 (768 1024) – Canon PowerShot S410 (768 1024) – Canon PowerShot G9 (768 1024) – Canon PowerShot SD600 (768 1024)

4 Sony DSC-W200 (750 1000) – Pentax Optio S5i (750 1000) – Fujifilm FinePix S1000fd (750 1000) – Canon PowerShot G7 (750 1000)

4 Sony DSC-W30 (1224 1632) – Sony DSC-T10 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)

4 Sony DSLR-A700 (2848 4272) – Canon EOS Kiss X2 (2848 4272) – Canon EOS DIGITAL REBEL XSi (2848 4272) – Canon EOS 450D (2848 4272)

4 Sony Ericsson K610i (1200 1600) – Sony Ericsson Z610i (1200 1600) – Sony Ericsson W880i (1200 1600) – Sony Ericsson W580i (1200 1600)

4 Sony Ericsson 5500i (1200 1600) – Sony Ericsson Z610i (1200 1600) – Sony Ericsson W580i (1200 1600) – Sony Ericsson W880i (1200 1600)

4 Sony Ericsson W800i (1224 1632) – Sony Ericsson K550i (1224 1632) – Sony Ericsson K750i (1224 1632) – Sony Ericsson W810i (1224 1632)

5 Aiptek International Inc. DV Ts (360 480) – Canon DIGITAL IXUS 40 (360 480) – Sony Ericsson K550i (360 480) – Fujifilm FinePix F47fd (360 480) – Olympus FE190/X750 (360 480)

5 Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon PowerShot SD1000 (2304 3072)

5 Canon DIGITAL IXUS 75 (1200 1600) – Canon PowerShot S200 (1200 1600) – Fujifilm FinePix Z20fd (1200 1600) – Konica Minolta DiMAGE Z10 (1200 1600) – Fujifilm FinePix S9600 (1200 1600)

5 Canon DIGITAL IXUS 860 IS (1536 2048) – Canon PowerShot A75 (1536 2048) – Canon PowerShot S1 IS (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon PowerShot S2 IS (1536 2048)

5 Canon EOS-1Ds Mark II (1000 1500) – Canon EOS DIGITAL REBEL XSi (1000 1500) – Canon EOS Kiss Digital X (1000 1500) – Canon EOS 30D (1000 1500) – Canon EOS 40D (1000 1500)

5 Canon EOS 20D (683 1024) – Canon EOS 30D (683 1024) – Canon EOS DIGITAL REBEL XTi (683 1024) – Canon EOS 400D DIGITAL (683 1024) – Canon EOS 350D DIGITAL (683 1024)

5 Canon EOS 300D DIGITAL (853 1280) – Canon EOS DIGITAL REBEL XT (853 1280) – Sony DSC-H10 (853 1280) – Canon EOS DIGITAL REBEL XTi (853 1280) – Canon EOS 350D DIGITAL (853 1280)

5 Canon EOS 30D (1371 2048) – Sony DSLR-A200 (1371 2048) – Nikon D40X (1371 2048) – Nikon D60 (1371 2048) – Nikon D80 (1371 2048)

5 Canon EOS 400D DIGITAL (532 800) – Nikon D50 (532 800) – Nikon D700 (532 800) – Pentax \*ist DS (532 800) – Canon EOS DIGITAL REBEL XTi (532 800)

5 Canon EOS D60 (2048 3072) – Sony DSC-P200 (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072) – Sony DSC-W55 (2048 3072) – Sony DSC-W35 (2048 3072)

5 Canon EOS DIGITAL REBEL (427 640) – Canon EOS DIGITAL REBEL XSi (427 640) – Canon EOS DIGITAL REBEL XTi (427 640) – Canon EOS 5D (427 640) – Sony DSLR-A700 (427 640)

5 Canon EOS DIGITAL REBEL XT (533 800) – Canon EOS 20D (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XTi (533 800) – Canon EOS 450D (533 800)

5 Canon EOS DIGITAL REBEL XT (533 800) – Canon EOS DIGITAL REBEL XTi (533 800) – Canon EOS 350D DIGITAL (533 800) – Canon EOS 40D (533 800) – Canon EOS 400D DIGITAL (533 800)

5 Canon EOS Kiss Digital X (2592 3888) – Canon EOS-1D Mark III (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888) – Canon EOS 40D (2592 3888)

5 Canon EOS Kiss Digital X (2592 3888) – Sony DSC-R1 (2592 3888) – Canon EOS 40D (2592 3888) – Canon EOS 400D DIGITAL (2592 3888) – Canon EOS DIGITAL REBEL XTi (2592 3888)

5 Canon IXY DIGITAL 2000 IS (3000 4000) – Canon DIGITAL IXUS 960 IS (3000 4000) – Canon PowerShot A650 IS (3000 4000) – Canon PowerShot SD950 IS (3000 4000) – Canon PowerShot G9 (3000 4000)

5 Canon IXY DIGITAL 800 IS (900 1200) – Canon PowerShot A610 (900 1200) – Sony Ericsson K750i (900 1200) – Panasonic DMC-TZ1 (900 1200) – Canon PowerShot S3 IS (900 1200)

5 Canon PowerShot A520 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Canon PowerShot A540 (1704 2272) – Nikon E4300 (1704 2272) – Nikon E4500 (1704 2272)

5 Canon PowerShot A520 (1704 2272) – Olympus u-miniD, Stylus V (1704 2272) – Canon PowerShot A80 (1704 2272) – Canon PowerShot G3 (1704 2272) – Olympus u20D, S400D, u400D (1704 2272)

5 Canon PowerShot A570 IS (480 640) – Canon PowerShot A95 (480 640) – Canon PowerShot S200 (480 640) – Canon PowerShot A430 (480 640) – Canon PowerShot S3 IS (480 640)

5 Canon PowerShot A610 (1944 2592) – Canon PowerShot A95 (1944 2592) – Canon PowerShot A530 (1944 2592) – Canon PowerShot SD400 (1944 2592) – Canon PowerShot SD750 (1944 2592)

5 Canon PowerShot A95 (1944 2592) – Canon PowerShot G5 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Canon PowerShot S500 (1944 2592) – Canon PowerShot SD800 IS (1944 2592)

5 Canon PowerShot SD600 (450 800) – Sony DSC-T200 (450 800) – Panasonic DMC-LX2 (450 800) – Panasonic DMC-TZ4 (450 800) – Panasonic DMC-TZ5 (450 800)

5 Canon PowerShot SD600 (600 800) – Canon PowerShot SD630 (600 800) – Panasonic DMC-TZ4 (600 800) – Olympus u720SW, S720SW (600 800) – Sony CYBERSHOT (600 800)

5 Canon PowerShot SD800 IS (900 1200) – Leica DIGILUX 2 (900 1200) – Canon PowerShot SD400 (900 1200) – Nikon COOLPIX S52c (900 1200) – Canon PowerShot A95 (900 1200)

5 Casio EX-Z700 (2048 3072) – Casio EX-Z70 (2048 3072) – Casio EX-Z750 (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072) – Canon EOS 10D (2048 3072)

5 Fujifilm FinePix J10 (2448 3264) – Olympus FE280, X820, C520 (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Olympus u850SW, S850SW (2448 3264) – Canon DIGITAL IXUS 860 IS (2448 3264)

5 Fujifilm FinePix S5600 (1944 2592) – Sony DSC-W15 (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Sony DSC-W5 (1944 2592) – Sony DSC-H50 (1944 2592)

5 Fujifilm FinePix S8000fd (2448 3264) – Olympus u820, S820 (2448 3264) – Olympus SP560UZ (2448 3264) – Olympus FE280, X820, C520 (2448 3264) – Fujifilm FinePix Z1000fd (2448 3264)

5 Fujifilm FinePix Z20fd (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

5 Hewlett-Packard PhotoSmart R717 (V01.00)d (957 1280) – Olympus C750UZ (957 1280) – Olympus C765UZ (957 1280) – Olympus X400, D580Z, C460Z (957 1280) – Olympus C770UZ (957 1280)

5 Nikon COOLPIX L6 (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Nikon E3200 (1536 2048) – Olympus X100, D540Z, C310Z (1536 2048) – Nikon E7600 (1536 2048)

5 Nikon COOLPIX P2 (1944 2592) – Olympus C5060WZ (1944 2592) – Nikon COOLPIX S200 (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Nikon COOLPIX L3 (1944 2592)

5 Nikon COOLPIX P50 (2448 3264) – Olympus FE340, X855, C560 (2448 3264) – Sony DSC-W90 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Nikon COOLPIX S210 (2448 3264)

5 Nikon D100 (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008) – Nikon D70s (2000 3008)

5 Nikon D100 (2000 3008) – Nikon D70 (2000 3008) – Nikon D70s (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)

5 Nikon D100 (2000 3008) – Nikon D70s (2000 3008) – Nikon D70 (2000 3008) – Nikon D40 (2000 3008) – Nikon D50 (2000 3008)

5 Nikon D100 (2000 3008) – Nikon D70s (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Nikon D40 (2000 3008)

5 Nikon D40X (2592 3872) – Pentax K10D (1071 1600) – Sony DSLR-A200 (2592 3872) – Nikon D200 (2592 3872) – Nikon D80 (2592 3872)

5 Nikon D60 (1071 1600) – Pentax K10D (1071 1600) – Nikon D40X (1071 1600) – Nikon D80 (1071 1600) – Nikon D200 (1071 1600)

5 Nikon D60 (535 800) – Sony DSLR-A100 (535 800) – Nikon D200 (535 800) – Nikon D40X (535 800) – Nikon D80 (535 800)

5 Nikon D700 (680 1024) – Canon EOS 40D (680 1024) – Nikon D90 (680 1024) – Nikon D300 (680 1024) – Canon EOS 5D (680 1024)

5 Nikon D70 (1362 2048) – Nikon D50 (1362 2048) – Pentax \*ist DL (1362 2048) – Nikon D40 (1362 2048) – Nikon D70s (1362 2048)

5 Nikon E3200 (1536 2048) – Nikon COOLPIX L3 (1536 2048) – Olympus X100, D540Z, C310Z (1536 2048) – Nikon E3100 (1536 2048) – Nikon E7600 (1536 2048)

5 Nikon E5000 (1920 2560) – Olympus SP570UZ (1920 2560) – Pentax Optio WP (1920 2560) – Polaroid Polaroid i532 (1920 2560) – Sony CYBERSHOT (1920 2560)

5 Nikon S1 (1944 2592) – Olympus D555Z, C315Z (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Nikon E5600 (1944 2592) – Nikon COOLPIX L3 (1944 2592)

5 Olympus C170, D425 (1712 2288) – Nikon E4100 (1712 2288) – Olympus C750UZ (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)

5 Olympus C5060WZ (1944 2592) – Nikon S1 (1944 2592) – Nikon E5600 (1944 2592) – Nikon COOLPIX L3 (1944 2592) – Olympus D555Z, C315Z (1944 2592)

5 Olympus C750UZ (1712 2288) – Nikon E4100 (1712 2288) – Olympus C765UZ (1712 2288) – Olympus C770UZ (1712 2288) – Nikon E4600 (1712 2288)

5 Olympus C765UZ (1712 2288) – Olympus X400, D580Z, C460Z (1712 2288) – Olympus C750UZ (1712 2288) – Olympus C170, D425 (1712 2288) – Nikon E4600 (1712 2288)

5 Olympus D595Z, C500Z (1920 2560) – Konica Minolta DiMAGE Z5 (1920 2560) – Panasonic DMC-TZ3 (1920 2560) – Olympus C5050Z (1920 2560) – Vivitar Vivi-Cam5355 (1920 2560)

5 Olympus FE340, X855, C560 (1920 2560) – Minolta DiMAGE F300 (1920 2560) – Olympus D595Z, C500Z (1920 2560) – Olympus C5050Z (1920 2560) – Nikon E5700 (1920 2560)

5 Olympus SP510UZ (2304 3072) – Olympus FE230/X790 (2304 3072) – Olympus SP550UZ (2304 3072) – Olympus FE240/X795 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)



5 Olympus SP560UZ (2448 3264) – Pentax Optio M40 (2448 3264) – Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix Z100fd (2448 3264) – Fujifilm FinePix S800fd (2448 3264)

5 Olympus SP570UZ (1920 2560) – Pentax Optio WP (1920 2560) – Nikon E5000 (1920 2560) – Olympus u1010,S1010 (1920 2560) – Nikon E5700 (1920 2560)

5 Olympus u1010,S1010 (2736 3648) – Olympus E-3 (2736 3648) – Olympus E-410 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648) – Olympus E-510 (2736 3648)

5 Olympus u1010,S1010 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648) – Olympus E-3 (2736 3648) – Olympus E-510 (2736 3648) – Olympus E-410 (2736 3648)

5 Olympus u790SW,S790SW (336 448) – Panasonic DMC-FZ7 (336 448) – Canon DIGITAL IXUS 70 (336 448) – Canon PowerShot A550 (336 448) – Canon PowerShot A530 (336 448)

5 Olympus X400,D580Z,C460Z (1712 2288) – Nikon E4100 (1712 2288) – Nikon E4800 (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)

5 Olympus X400,D580Z,C460Z (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4100 (1712 2288) – Olympus C750UZ (1712 2288) – Nikon E4600 (1712 2288)

5 Panasonic DMC-FX33 (480 640) – Canon PowerShot A540 (480 640) – Panasonic DMC-FX35 (480 640) – Sony DSC-P200 (480 640) – Canon PowerShot SD870 IS (480 640)

5 Panasonic DMC-FZ18 (1920 2560) – Panasonic DMC-TZ1 (1920 2560) – Panasonic DMC-LS2 (1920 2560) – Panasonic DMC-LZ2 (1920 2560) – Panasonic DMC-LZ3 (1920 2560)

5 Panasonic DMC-FZ7 (1728 2304) – Sony DSC-L1 (1728 2304) – Sony DSC-S60 (1728 2304) – Sony DSC-S90 (1728 2304) – Sony DSC-S40 (1728 2304)

5 Panasonic DMC-LZ6 (1920 2560) – Panasonic DMC-FX12 (1920 2560) – Panasonic DMC-TZ4 (1920 2560) – Panasonic DMC-FZ8 (1920 2560) – Panasonic DMC-FX35 (1920 2560)

5 Panasonic DMC-TZ5 (900 1600) – Leica D-LUX 3 (900 1600) – Panasonic DMC-TZ1 (900 1600) – Canon PowerShot SD800 IS (900 1600) – Panasonic DMC-LX2 (900 1600)

5 Pentax K100D (1064 1600) – Nikon D70s (1064 1600) – Nikon D50 (1064 1600) – Nikon D40 (1064 1600) – Nikon D100 (1064 1600)

5 Pentax K100D (1861 2800) – Nikon D70s (1861 2800) – Nikon D50 (1861 2800) – Nikon D70 (1861 2800) – Nikon D40 (1861 2800)

5 Pentax K100D (2000 3008) – Nikon D70s (2000 3008) – Nikon D70 (2000 3008) – Nikon D40 (2000 3008) – Nikon D50 (2000 3008)

5 Pentax Optio S6 (1200 1600) – Casio EX-Z850 (1200 1600) – Nikon E775 (1200 1600) – Nikon E2100 (1200 1600) – Sony CYBERSHOT (1200 1600)

5 Pentax Optio WPi (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Nikon COOLPIX L6 (2112 2816)

5 Pentax Pentax K200D (2592 3872) – Pentax K200D (2592 3872) – Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D80 (2592 3872)

5 Research In Motion BlackBerry 8110 (400 528) – Research In Motion BlackBerry 8130 (400 528) – Research In Motion BlackBerry 8320 (400 528) – Research In Motion BlackBerry 8330 (400 528) – Research In Motion BlackBerry 8310 (400 528)

5 Research In Motion BlackBerry 8130 (768 1024) – Research In Motion BlackBerry 8330 (768 1024) – Research In Motion BlackBerry 8320 (768 1024) – Research In Motion BlackBerry 8310 (768 1024) – Research In Motion BlackBerry 8300 (768 1024)

5 Sony CYBERSHOT (1536 2048) – Sony DSC-W50 (1536 2048) – Sony DSC-W55 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-T50 (1536 2048)

5 Sony DSC-H2 (1224 1632) – Sony DSC-W100 (1224 1632) – Sony DSC-T10 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)

5 Sony DSC-H7 (2176 3264) – Sony DSC-W90 (2176 3264) – Sony DSC-T100 (2176 3264) – Sony DSC-T200 (2176 3264) – Sony DSC-H3 (2176 3264)

5 Sony DSC-H7 (480 640) – Sony DSC-W120 (480 640) – Sony DSC-W55 (480 640) – Sony DSC-W80 (480 640) – Sony DCR-HC32E (480 640)

5 Sony DSC-P150 (2304 3072) – Sony DSC-W55 (2304 3072) – Sony DSC-W35 (2304 3072) – Fujifilm FinePix S5700 5700 (2304 3072) – Sony DSC-W80 (2304 3072)

5 Sony DSC-P200 (480 640) – Sony DSC-T9 (480 640) – Sony DSC-W55 (480 640) – Sony DSC-L1 (480 640) – Sony DSC-T5 (480 640)

5 Sony DSC-S650 (600 800) – Olympus u710,S710 (600 800) – Sony DSC-N2 (600 800) – Fujifilm FinePix S9600 (600 800) – Panasonic DMC-FZ5 (600 800)

5 Sony DSC-T50 (1224 1632) – Sony DSC-W30 (1224 1632) – Sony DSC-T100 (1224 1632) – Sony DSC-W55 (1224 1632) – Sony DSC-W50 (1224 1632)

5 Sony DSC-T5 (1728 2592) – Sony DSC-P10 (1728 2592) – Sony DSC-P100 (1728 2592) – Sony DSC-T33 (1728 2592) – Sony DSC-H1 (1728 2592)

5 Sony DSC-W150 (2176 3264) – Sony DSC-T100 (2176 3264) – Sony DSC-H3 (2176 3264) – Sony DSC-T200 (2176 3264) – Sony DSC-H7 (2176 3264)

5 Sony DSC-W1 (960 1280) – Sony DSC-P92 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P43 (960 1280) – Sony DSC-P10 (960 1280)

5 Sony DSC-W70 (768 1024) – Canon DIGITAL IXUS 850 IS (768 1024) – Sony CYBERSHOT (768 1024) – Pentax Optio M20 (768 1024) – Sony DSC-T300 (768 1024)

5 Sony DSLR-A300 (2592 3872) – Nikon D80 (2592 3872) – Pentax K10D (2592 3872) – Sony DSLR-A100 (2592 3872) – Sony DSLR-A200 (2592 3872)

5 Sony MVC-CD350 (1536 2048) – Sony CD MAVICA (1536 2048) – Sony DSC-P10 (1536 2048) – Sony DSC-P8 (1536 2048) – Sony CYBERSHOT (1536 2048)

6 Canon DIGITAL IXUS 60 (2112 2816) – Canon PowerShot SD700 IS (2112 2816) – Canon PowerShot SD630 (2112 2816) – Canon PowerShot A540 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Canon PowerShot S3 IS (2112 2816)

6 Canon EOS 10D (2048 3072) – Canon EOS 300D DIGITAL (2048 3072) – Sony DSC-W55 (2048 3072) – Sony DSC-W35 (2048 3072) – Canon EOS DIGITAL REBEL (2048 3072) – Sony DSC-P200 (2048 3072)

6 Canon EOS 350D DIGITAL (667 1000) – Canon EOS DIGITAL REBEL XTi (667 1000) – Canon EOS 30D (667 1000) – Canon EOS 450D (667 1000) – Canon EOS 400D DIGITAL (667 1000) – Canon EOS 40D (667 1000)

6 Canon EOS 350D DIGITAL (800 1200) – Canon PowerShot A720 IS (800 1200) – Canon EOS 20D (800 1200) – Canon EOS 400D DIGITAL (800 1200) – Canon EOS 40D (800 1200) – Canon EOS DIGITAL REBEL XTi (800 1200)

6 Canon EOS 450D (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XT (533 800) – Canon EOS 300D DIGITAL (533 800) – Canon EOS 20D (533 800) – Canon EOS DIGITAL REBEL XTi (533 800)

6 Canon EOS D30 (427 640) – Canon EOS 20D (427 640) – Canon EOS DIGITAL REBEL XSi (427 640) – Canon EOS 400D DIGITAL (427 640) – Canon EOS DIGITAL REBEL XTi (427 640) – Canon EOS DIGITAL REBEL XT (427 640)

6 Canon PowerShot A550 (1728 3072) – Canon PowerShot A570 IS (1728 3072) – Canon PowerShot SD750 (1728 3072) – Canon PowerShot SD1000 (1728 3072) – Canon PowerShot TX1 (1728 3072) – Canon PowerShot SD800 IS (1728 3072)

6 Canon PowerShot SD880 IS (2736 3648) – Canon PowerShot SD890 IS (2736 3648) – Canon PowerShot A640 (2736 3648) – Canon PowerShot SD790 IS (2736 3648) – Canon PowerShot SD900 (2736 3648) – Canon PowerShot G7 (2736 3648)

6 Canon PowerShot SX100 IS (1832 3264) – Canon PowerShot SD870 IS (1832 3264) – Canon PowerShot A720 IS (1832 3264) – Canon PowerShot SD850 IS (1832 3264) – Canon PowerShot S5 IS (1832 3264) – Canon PowerShot SD1100 IS (1832 3264)

6 Canon PowerShot SX100 IS (600 800) – Sony DSC-N2 (600 800) – Sony DSC-V1 (600 800) – Sony DSC-W70 (600 800) – Casio EX-Z50 (600 800) – Sony DSC-P200 (600 800)

6 Casio EX-S600 (2112 2816) – Casio EX-Z110 (2112 2816) – Casio EX-Z600 (2112 2816) – Pentax Optio W10 (2112 2816) – Olympus FE190/X750 (2112 2816) – Sony DSC-H2 (2112 2816)

6 Casio EX-Z1080 (1200 1600) – Casio EX-Z80 (1200 1600) – Casio EX-Z77 (1200 1600) – Casio EX-V8 (1200 1600) – Casio EX-Z1050 (1200 1600) – Casio EX-Z100 (1200 1600)

6 Casio EX-Z120 (2304 3072) – Olympus u790SW,S790SW (2304 3072) – Olympus FE230/X790 (2304 3072) – Sony DSC-S700 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Sony DSC-W55 (2304 3072)

6 Fujifilm FinePix F11 (960 1280) – Sanyo E1 (960 1280) – Canon PowerShot S3 IS (960 1280) – Canon PowerShot SD450 (960 1280) – Samsung <Digimax S500 / Kenox S500 / Digimax Cyber 530> (960 1280) – Sony DSC-W90 (960 1280)

6 Fujifilm FinePix S5700 5700 (2304 3072) – Sony DSC-W70 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W55 (2304 3072) – Sony DSC-P150 (2304 3072) – Sony DSC-W35 (2304 3072)

6 Fujifilm FinePix S8100fd (2736 3648) – Olympus u1030SW,S1030SW (2736 3648) – Ricoh R8 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Olympus E-520 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

6 Fujifilm FinePix Z20fd (2736 3648) – Olympus SP570UZ (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

6 Konica Minolta DYNAX 5D (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Seiko EPSON R-D1 (2000 3008) – Nikon D70s (2000 3008) – Nikon D40 (2000 3008)

6 Leica C-LUX 2 (2304 3072) – Panasonic DMC-LS75 (2304 3072) – Panasonic DMC-FX30 (2304 3072) – Panasonic DMC-LZ7 (2304 3072) – Panasonic DMC-FX12 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)

6 Leica C-LUX 2 (2304 3072) – Panasonic DMC-LS75 (2304 3072) – Panasonic DMC-LZ7 (2304 3072) – Panasonic DMC-FX30 (2304 3072) – Panasonic DMC-FX12 (2304 3072) – Panasonic DMC-FZ8 (2304 3072)

6 Nikon COOLPIX L14 (1944 2592) – Nikon E5600 (1944 2592) – Nikon COOLPIX S200 (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Olympus D555Z,C315Z (1944 2592)

6 Nikon COOLPIX P80 (1536 2048) – Nikon COOLPIX S10 (1536 2048) – Nikon E3100 (1536 2048) – Nikon E3200 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Nikon E7600 (1536 2048)

6 Nikon COOLPIX P80 (1536 2048) – Nikon COOLPIX S10 (1536 2048) – Nikon E995 (1536 2048) – Nikon E3100 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Nikon E7600 (1536 2048)

6 Nikon COOLPIX S10 (2112 2816) – Olympus FE190/X750 (2112 2816) – Sanyo VPC-S600 (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Olympus SP500UZ (2112 2816) – Digital Camera 6MP-9FW (2112 2816)

6 Nikon D40X (2592 3872) – Sony DSLR-A300 (2592 3872) – Pentax K10D (2592 3872) – Nikon D60 (2592 3872) – Nikon D80 (2592 3872) – Nikon D200 (2592 3872)

6 Nikon D60 (535 800) – Nikon D200 (535 800) – Sony DSLR-A100 (535 800) – Nikon D40X (535 800) – Panasonic DMC-TZ4 (535 800) – Nikon D80 (535 800)

6 Nikon E2200 (1200 1600) – Nikon E3500 (1200 1600) – Olympus C700UZ (1200 1600) – Nikon E4100 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Nikon E2100 (1200 1600)

6 Nikon E4500 (1704 2272) – Sony CYBERSHOT (1704 2272) – Nikon E4300 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Sony CD MAVICA (1704 2272) – Samsung ELECTRONICS SCD6040 (1704 2272)

6 Nikon E775 (1200 1600) – Olympus C700UZ (1200 1600) – Research In Motion BlackBerry 8310 (1200 1600) – Konica Minolta DiMAGE Z10 (1200 1600) – Konica Minolta DiMAGE X50 (1200 1600) – Nikon E2100 (1200 1600)

6 Olympus C5060WZ (1944 2592) – Nikon COOLPIX S550 (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Nikon E5600 (1944 2592) – Olympus D555Z,C315Z (1944 2592) – Nikon COOLPIX P2 (1944 2592)

6 Olympus E-420 (2736 3648) – Olympus E-3 (2736 3648) – Olympus E-410 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Olympus E-510 (2736 3648) – Olympus u1030SW,S1030SW (2736 3648)

6 Olympus u820,S820 (2448 3264) – Pentax Optio L40 (2448 3264) – Olympus SP560UZ (2448 3264) – Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Fujifilm FinePix Z100fd (2448 3264)

6 Panasonic DMC-FS5 (2736 3648) – Panasonic DMC-FS20 (2736 3648) – Panasonic DMC-FX36 (2736 3648) – Panasonic DMC-FX500 (2736 3648) – Panasonic DMC-FX35 (2736 3648) – Panasonic DMC-FZ28 (2736 3648)

6 Panasonic DMC-FX55 (2448 3264) – Panasonic DMC-LS80 (2448 3264) – Panasonic DMC-LZ8 (2448 3264) – Panasonic DMC-FX33 (2448 3264) – Panasonic DMC-FS3 (2448 3264) – Panasonic DMC-TZ4 (2448 3264)

6 Panasonic DMC-FZ20 (1920 2560) – Panasonic DMC-FZ5 (1920 2560) – Panasonic DMC-FZ30 (1920 2560) – Nikon E5700 (1920 2560) – Sony CYBERSHOT (1920 2560) – Nikon E5000 (1920 2560)

6 Panasonic DMC-LX3 (2736 3648) – Panasonic DMC-FX36 (2736 3648) – Panasonic DMC-FX500 (2736 3648) – Panasonic DMC-FS5 (2736 3648) – Panasonic DMC-FZ28 (2736 3648) – Panasonic DMC-FX35 (2736 3648)

6 Pentax \*ist DL (1024 1280) – T-Mobile(R) Sidekick Slide (1024 1280) – T-Mobile(R) Sidekick LX (1024 1280) – T-Mobile(R) Sidekick 2008 (1024 1280) – T-Mobile(R) Sidekick(R) 3 (1024 1280) – Research In Motion BlackBerry 8100 Series (1024 1280)

6 Pentax K10D (1071 1600) – Sony DSLR-A300 (1071 1600) – Nikon D60 (1071 1600) – Nikon D40X (1071 1600) – Nikon D200 (1071 1600) – Nikon D80 (1071 1600)

6 Pentax K20D (2592 3872) – Nikon D60 (2592 3872) – Nikon D40X (2592 3872) – Nikon D200 (2592 3872) – Nikon D80 (2592 3872) – Pentax K10D (2592 3872)

6 Pentax Optio S4i (1728 2304) – Pentax Optio S40 (1728 2304) – Panasonic DMC-FZ7 (1728 2304) – Casio EX-Z60 (1728 2304) – Sony DSC-P41 (1728 2304) – Pentax Optio S4 (1728 2304)

6 Research In Motion BlackBerry 8120 (1200 1600) – Research In Motion BlackBerry 8300 (1200 1600) – Research In Motion BlackBerry 8320 (1200 1600) – Research In Motion BlackBerry 8130 (1200 1600) – Research In Motion BlackBerry 8310 (1200 1600) – Research In Motion BlackBerry 8330 (1200 1600)

6 Samsung NV24HD, VLUU NV24HD, LANDIAO NV106HD (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Samsung <KENOX S1050 / Samsung S1050> (2736 3648) – Casio EX-S10 (2736 3648) – Olympus E-510 (2736 3648) – Fujifilm FinePix S8100fd (2736 3648)

6 Sony DSC-F88 (1536 2048) – Sony DSC-P120 (1536 2048) – Sony DSC-P73 (1536 2048) – Sony DSC-P93 (1536 2048) – Sony DSC-P100 (1536 2048) – Sony DSC-W1 (1536 2048)

6 Sony DSC-H9 (2448 3264) – Olympus C8080WZ (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-W90 (2448 3264) – Nikon COOLPIX S210 (2448 3264)

6 Sony DSC-W70 (960 1280) – Panasonic DMC-FZ18 (960 1280) – Nikon COOLPIX S50c (960 1280) – Panasonic DMC-LZ2 (960 1280) – Sony DSC-H1 (960 1280) – Canon PowerShot G9 (960 1280)

6 Sony Ericsson K550i (1224 1632) – Sony Ericsson W610i (1224 1632) – Sony Ericsson K750i (1224 1632) – Sony Ericsson W800i (1224 1632) – Sony Ericsson K800i (1224 1632) – Sony Ericsson W810i (1224 1632)

6 T-Mobile(R) Sidekick LX (1024 1280) – Centro (1024 1280) – Treo 700p (1024 1280) – Treo 755p (1024 1280) – T-Mobile Dash T-Mobile Dash (1024 1280) – Palm Centro (1024 1280)

7 Canon (1704 2272) – Canon PowerShot A520 (1704 2272) – Canon PowerShot S3 IS (1704 2272) – Canon PowerShot SD300 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Nikon E4300 (1704 2272) – Nikon E4500 (1704 2272)

7 Canon EOS 350D DIGITAL (683 1024) – Canon EOS DIGITAL REBEL XSi (683 1024) – Canon EOS 30D (683 1024) – Canon EOS 40D (683 1024) – Canon EOS 400D DIGITAL (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024) – Canon EOS DIGITAL REBEL XTi (683 1024)

7 Canon EOS 400D DIGITAL (683 1024) – Canon EOS DIGITAL REBEL (683 1024) – Canon PowerShot S5 IS (683 1024) – Sony DSC-W80 (683 1024) – Canon EOS DIGITAL REBEL XSi (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024) – Canon EOS 20D (683 1024)

7 Canon PowerShot SD790 IS (768 1024) – Nikon COOLPIX S200 (768 1024) – Pentax Optio M20 (768 1024) – Canon PowerShot A540 (768 1024) – Nikon E7600 (768 1024) – Nikon COOLPIX L3 (768 1024) – Canon PowerShot SD870 IS (768 1024)

7 Fujifilm FinePix Z20fd (2736 3648) – Olympus SP570UZ (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

7 Nikon COOLPIX L2 (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Olympus SP500UZ (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Nikon COOLPIX S4 (2112 2816)

7 Nikon COOLPIX S550 (1944 2592) – Olympus C5060WZ (1944 2592) – Nikon E5600 (1944 2592) – Olympus D555Z,C315Z (1944 2592) – Nikon COOLPIX L14 (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Nikon COOLPIX S210 (1944 2592)

7 Nikon D70s (2000 3008) – Pentax \*ist DS (2000 3008) – Pentax K100D (2000 3008) – Nikon D70 (2000 3008) – Nikon D50 (2000 3008) – Pentax \*ist DL (2000 3008) – Nikon D40 (2000 3008)

7 Olympus D595Z,C500Z (1920 2560) – Nikon E5700 (1920 2560) – Olympus u1010,S1010 (1920 2560) – Olympus C5050Z (1920 2560) – Panasonic DMC-FS5 (1920 2560) – Canon PowerShot A530 (1920 2560) – Panasonic DMC-FZ20 (1920 2560)

7 Olympus u1000/S1000 (2736 3648) – Olympus SP570UZ (2736 3648) – Olympus u1010,S1010 (2736 3648) – Sony DSC-T700 (2736 3648) – Sony DSC-N2 (2736 3648) – Sony DSC-W170 (2736 3648) – Sony DSC-T300 (2736 3648)

7 Olympus u850SW,S850SW (960 1280) – Sony DSC-P200 (960 1280) – Sony DSC-P100 (960 1280) – Sony DSC-T33 (960 1280) – Sony DSC-T1 (960 1280) – Sony DSC-H1 (960 1280) – Olympus E-510 (960 1280)

7 Olympus X250,D560Z,C350Z (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Nikon E3100 (1536 2048) – Nikon E7600 (1536 2048) – Olympus C740UZ (1536 2048) – Nikon E3200 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048)

7 Olympus X400,D580Z,C460Z (1712 2288) – Nikon E4600 (1712 2288) – Olympus C170,D425 (1712 2288) – Olympus C770UZ (1712 2288) – Olympus C765UZ (1712 2288) – Olympus C4100Z,C4000Z (1712 2288)

7 Panasonic DMC-FS3 (600 800) – Sony DSC-P200 (600 800) – Panasonic DMC-TZ3 (600 800) – Sony DSC-F828 (600 800) – Sony DSC-V1 (600 800) – Canon PowerShot SD1000 (600 800) – Olympus E-400 (600 800)

7 Pentax \*ist D52 (1361 2048) – Nikon D50 (1361 2048) – Sony DSC-S600 (1361 2048) – Nikon D70 (1361 2048) – Nikon D70s (1361 2048) – Nikon D40 (1361 2048) – Canon EOS-1D Mark III (1361 2048)

7 Pentax K10D (857 1280) – Sony DSLR-A100 (857 1280) – Nikon D200 (857 1280) – Sony DSLR-A200 (857 1280) – Nikon D60 (857 1280) – Nikon D40X (857 1280) – Nikon D80 (857 1280)

7 Ricoh R8 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

7 Samsung VLUU L100, M100 / Samsung L100, M100 (768 1024) – Supra DC 7900 (768 1024) – Canon DIGITAL IXUS 80 IS (768 1024) – Panasonic DMC-TZ3 (768 1024) – Canon DIGITAL IXUS 950 IS (768 1024) – Panasonic DMC-TZ5 (768 1024) – Casio EX-Z750 (768 1024)

7 SeaLife SL320/SL321 (480 640) – Sony DSC-H3 (480 640) – Sony DSC-W55 (480 640) – Sony DSC-W80 (480 640) – Canon PowerShot SD790 IS (480 640) – Canon PowerShot A550 (480 640) – Canon PowerShot SD870 IS (480 640)

7 Sony DSC-H1 (1944 2592) – Nikon S1 (1944 2592) – Nikon E5600 (1944 2592) – Olympus D555Z,C315Z (1944 2592) – Sony DSC-W80 (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Nikon COOLPIX L3 (1944 2592)

7 Sony DSC-H7 (1080 1920) – Sony DSC-W100 (1080 1920) – Sony DSC-H3 (1080 1920) – Sony DSC-T200 (1080 1920) – Sony DSC-W55 (1080 1920) – Sony DSC-T50 (1080 1920) – Sony DSC-T70 (1080 1920)

7 Sony DSC-H9 (2176 3264) – Sony DSC-W150 (2176 3264) – Sony DSC-H3 (2176 3264) – Sony DSC-T70 (2176 3264) – Sony DSC-T100 (2176 3264) – Sony DSC-T200 (2176 3264) – Sony DSC-H7 (2176 3264)

7 Sony DSC-M1 (1944 2592) – Sony DSC-F828 (1944 2592) – Sony DSC-P93A (1944 2592) – Sony DSC-T1 (1944 2592) – Sony DSC-W1 (1944 2592) – Sony DSC-P93 (1944 2592) – Sony DSC-P100 (1944 2592)

7 Sony DSC-M2 (768 1024) – Sony DSC-W70 (768 1024) – Fujifilm FinePix A330 (768 1024) – Sony DSC-W5 (768 1024) – Canon PowerShot SX100 IS (768 1024) – Sony DSC-T300 (768 1024) – Pentax Optio M20 (768 1024)

7 Sony DSC-P150 (960 1280) – Minolta DiMAGE Z1 (960 1280) – Sony DSC-P200 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P10 (960 1280) – Olympus E-510 (960 1280) – Sony DSC-H1 (960 1280)

7 Sony DSLR-A300 (1370 2048) – Sony DSLR-A200 (1370 2048) – Nikon D40X (1370 2048) – Nikon D60 (1370 2048) – Nikon D200 (1370 2048) – Sony DSLR-A100 (1370 2048) – Nikon D80 (1370 2048)

8 Canon DIGITAL IXUS 750 (600 800) – Canon PowerShot A620 (600 800) – Canon PowerShot S3 IS (600 800) – Canon PowerShot SD750 (600 800) – Canon PowerShot SD1000 (600 800) – Canon PowerShot S1 IS (600 800) – Canon PowerShot A510 (600 800) – Canon DIGITAL IXUS 55 (600 800)

8 Canon EOS 20D (683 1024) – Canon EOS 40D (683 1024) – Canon EOS 50D (683 1024) – Canon EOS 5D (683 1024) – Canon EOS DIGITAL REBEL XTi (683 1024) – Canon EOS 450D (683 1024) – Canon EOS 30D (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024)

8 Canon EOS 30D (1066 1600) – Canon EOS 20D (1066 1600) – Canon EOS DIGITAL REBEL XT (1066 1600) – Canon EOS 350D DIGITAL (1066 1600) – Canon EOS DIGITAL REBEL XSi (1066 1600) – Canon EOS DIGITAL REBEL XTi (1066 1600) – Canon EOS 400D DIGITAL (1066 1600) – Canon EOS 40D (1066 1600)

8 Canon EOS 350D DIGITAL (681 1024) – Canon EOS 450D (681 1024) – Canon EOS DIGITAL REBEL XTi (681 1024) – Canon EOS 30D (681 1024) – Canon EOS DIGITAL REBEL XSi (681 1024) – Canon EOS 5D (681 1024) – Nikon D100 (681 1024) – Nikon D40 (681 1024)

8 Canon EOS 450D (533 800) – Canon EOS DIGITAL REBEL XTi (533 800) – Canon EOS 5D (533 800) – Canon PowerShot SD30 (533 800) – Canon EOS 350D DIGITAL (533 800) – Canon EOS 40D (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XT (533 800)

8 Canon EOS DIGITAL REBEL XT (682 1024) – Nikon D80 (682 1024) – Canon EOS Kiss Digital X (682 1024) – Canon EOS 20D (682 1024) – Canon EOS 50D (682 1024) – Canon EOS 400D DIGITAL (682 1024) – Canon EOS 5D (682 1024) – Canon EOS DIGITAL REBEL XTi (682 1024)

8 Canon EOS DIGITAL REBEL XT (683 1024) – Nikon D50 (683 1024) – Sony DSC-R1 (683 1024) – Canon EOS 50D (683 1024) – Canon EOS 5D (683 1024) – Canon EOS 40D (683 1024) – Canon EOS 400D DIGITAL (683 1024) – Canon EOS DIGITAL REBEL XTi (683 1024)

8 Canon EOS DIGITAL REBEL XTi (532 800) – Nikon D100 (532 800) – Nikon D70s (532 800) – Sony DSC-W50 (532 800) – Canon EOS 40D (532 800) – Nikon D50 (532 800) – Nikon D70 (532 800) – Nikon D40 (532 800)

8 Canon PowerShot A530 (1944 2592) – Nikon COOLPIX L3 (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Canon PowerShot S5 IS (1944 2592) – Nikon E5600 (1944 2592) – Olympus C5060WZ (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Olympus D5555\_C315Z (1944 2592)

8 Canon PowerShot A540 (1704 2272) – Canon PowerShot A80 (1704 2272) – Nikon E4300 (1704 2272) – Nikon E4500 (1704 2272) – Canon PowerShot SD600 (1704 2272) – Canon PowerShot S3 IS (1704 2272) – Canon PowerShot A520 (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272)

8 Canon PowerShot A630 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Canon PowerShot SD450 (1944 2592) – Canon PowerShot SD20 (1944 2592) – Canon PowerShot A530 (1944 2592) – Canon PowerShot A650 IS (1944 2592) – Canon PowerShot A95 (1944 2592) – Canon PowerShot SD1100 IS (1944 2592)

8 Nikon COOLPIX S210 (2448 3264) – Canon PowerShot A630 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Olympus SP350 (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Olympus FE250/X800 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Fujifilm FinePix J50 (2448 3264)

8 Nikon E4500 (856 1280) – Nikon D60 (856 1280) – Pentax K10D (856 1280) – Sony DSLR-A100 (856 1280) – Sony DSLR-A200 (856 1280) – Nikon D40X (856 1280) – Nikon D80 (856 1280) – Nikon D200 (856 1280)

8 Nikon E5200 (1944 2592) – Sony DSC-T1 (1944 2592) – Canon PowerShot G9 (1944 2592) – Sony DSC-P93A (1944 2592) – Sony DSC-W5 (1944 2592) – Fujifilm FinePix Z1 (1944 2592) – Sony DSC-T7 (1944 2592) – Sony DSC-H1 (1944 2592)

8 Nikon E7600 (2304 3072) – Olympus FE240/X795 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus SP310 (2304 3072) – Olympus SP510UZ (2304 3072) – Olympus SP550UZ (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Olympus FE230/X790 (2304 3072)

8 Nikon E7600 (2304 3072) – Olympus SP550UZ (2304 3072) – Sony DSC-H5 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Sony DSC-W120 (2304 3072) – Sony DSC-P150 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-W55 (2304 3072)

8 Olympus SP510UZ (2304 3072) – Nikon E7600 (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Olympus FE240/X795 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus SP550UZ (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Olympus FE230/X790 (2304 3072)

8 Panasonic DMC-FX12 (2304 3072) – Canon DIGITAL IXUS 700 (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Panasonic DMC-TZ3 (2304 3072) – Sony DSC-W80 (2304 3072) – Canon PowerShot SD1000 (2304 3072)

8 Pentax \*ist DL2 (2000 3008) – Pentax K110D (2000 3008) – Samsung GX-1L (2000 3008) – Samsung GX-1S (2000 3008) – Pentax \*ist DL (2000 3008) – Pentax K100D Super (2000 3008) – Pentax K100D (2000 3008) – Pentax \*ist DS (2000 3008)

8 Pentax K10D (851 1280) – Pentax K100D (851 1280) – Nikon D70s (851 1280) – Nikon D100 (851 1280) – Pentax K110D (851 1280) – Nikon D70 (851 1280) – Nikon D40 (851 1280) – Nikon D50 (851 1280)

8 Pentax Optio S5n (1920 2560) – Olympus SP570UZ (1920 2560) – Casio EX-Z1000 (1920 2560) – Casio EX-Z75 (1920 2560) – Casio EX-Z70 (1920 2560) – Casio EX-S500 (1920 2560) – Pentax Optio S5i (1920 2560) – Pentax Optio S5z (1920 2560)

8 Sony CD MAVICA (1704 2272) – Konica Minolta Camera, Inc. DiMAGE Z2 (1704 2272) – Sony CYBERSHOT (1704 2272) – Canon PowerShot A85 (1704 2272) – Canon PowerShot A80 (1704 2272) – Canon PowerShot 5400 (1704 2272) – Nikon E4500 (1704 2272) – Samsung ELECTRONICS SC2D6040 (1704 2272)

8 Sony DSC-H2 (1224 1632) – Sony DSC-S600 (1224 1632) – Sony Ericsson K800i (1224 1632) – Sony DSC-T70 (1224 1632) – Sony DSC-T10 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)

8 Sony DSC-H3 (480 640) – Sony DSC-T9 (480 640) – Sony DSC-W120 (480 640) – Sony DSC-H7 (480 640) – Nikon COOLPIX P80 (480 640) – Sony DSC-W55 (480 640) – Sony CLIE (480 640) – Sony DSC-T1 (480 640)

8 Sony DSC-S60 (1728 2304) – Sony DSC-L1 (1728 2304) – Panasonic DMC-FZ7 (1728 2304) – Sony DSC-S90 (1728 2304) – Pentax OptioE20 (1728 2304) – Sony DSC-P73 (1728 2304) – Sony DSC-P41 (1728 2304) – Sony DSC-S40 (1728 2304)

8 Sony DSC-W30 (2112 2816) – Fujifilm FinePix F650 (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Pentax Optio W10 (2112 2816) – Sony DSC-H2 (2112 2816) – Olympus FE190/X750 (2112 2816) – Olympus SP500UZ (2112 2816) – Olympus FE-120,X-700 (2112 2816)

9 Canon EOS 450D (683 1024) – Canon EOS 400D DIGITAL (683 1024) – SIGMA SIGMA DP1 (683 1024) – Canon EOS-1Ds Mark II (683 1024) – Canon EOS 20D (683 1024) – Canon EOS DIGITAL REBEL XSi (683 1024) – Canon EOS DIGITAL REBEL XTi (683 1024) – Canon EOS DIGITAL REBEL XT (683 1024) – Canon EOS 5D (683 1024)

9 Canon PowerShot A430 (768 1024) – Canon PowerShot SD870 IS (768 1024) – Nikon COOLPIX L11 (768 1024) – Panasonic DMC-TZ3 (768 1024) – Panasonic DMC-FZ8 (768 1024) – Olympus SP510UZ (768 1024) – Nikon E7600 (768 1024) – Olympus u30D,S410D,u410D (768 1024) – Canon DIGITAL IXUS 980 IS (768 1024)

9 Canon PowerShot A520 (1704 2272) – Canon PowerShot A540 (1704 2272) – Canon PowerShot SD300 (1704 2272) – Canon PowerShot SX110 IS (1704 2272) – Canon PowerShot 5400 (1704 2272) – Canon PowerShot SD630 (1704 2272) – Canon PowerShot S410 (1704 2272) – Canon PowerShot A430 (1704 2272) – Canon PowerShot SD600 (1704 2272)

9 Casio EX-Z3 (768 1024) – Sony DSC-W35 (768 1024) – Sony DSC-W50 (768 1024) – Panasonic DMC-TZ5 (768 1024) – Samsung NV24HD, VLUU NV24HD, LANDIAO NV106HD (768 1024) – Sony DSC-W5 (768 1024) – Fujifilm FinePix A330 (768 1024) – Panasonic DMC-FZ18 (768 1024) – Pentax Optio M20 (768 1024)

9 Casio EX-Z850 (2448 3264) – Samsung VLUU L100, M100 / Samsung L100, M100 (2448 3264) – Panasonic DMC-FZ30 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Nikon E8700 (2448 3264) – Panasonic DMC-FS3 (2448 3264) – Olympus FE250/X800 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264)

9 Fujifilm FinePix S8000fd (2448 3264) – Olympus SP350 (2448 3264) – Sony DSC-W90 (2448 3264) – Canon PowerShot S80 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-H10 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Canon PowerShot S5 IS (2448 3264)

9 Olympus C70Z,C700Z (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Sony DSC-W120 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W55 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-W80 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

9 Olympus D595Z,C500Z (1920 2560) – Olympus FE310,X840,C530 (1920 2560) – Nikon E5700 (1920 2560) – Panasonic DMC-FZ5 (1920 2560) – Samsung Digimax A503 / Kenox D503 (1920 2560) – Olympus C5050Z (1920 2560) – Polaroid i531 (1920 2560) – Panasonic DMC-FZ8 (1920 2560) – Panasonic DMC-TZ1 (1920 2560)

9 Olympus SP510UZ (2304 3072) – Olympus SP550UZ (2304 3072) – Sony DSC-P150 (2304 3072) – Sony DSC-P200 (2304 3072) – Casio EX-S770 (2304 3072) – Olympus FE230/X790 (2304 3072) – Sony DSC-W55 (2304 3072) – Sony DSC-H5 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

9 Olympus u710,S710 (600 800) – Canon PowerShot A430 (600 800) – Canon PowerShot SD750 (600 800) – Nikon E8700 (600 800) – Olympus E-410 (600 800) – Canon PowerShot SD1100 IS (600 800) – Fujifilm FinePix S9600 (600 800) – Canon PowerShot G7 (600 800) – Olympus C70Z,C7000Z (600 800)

9 Panasonic DMC-FZ8 (532 800) – Canon EOS 40D (532 800) – Pentax K20D (532 800) – Pentax \*ist DL (532 800) – Pentax K100D (532 800) – Nikon D70 (532 800) – Nikon D50 (532 800) – Nikon D40 (532 800) – Nikon D300 (531 800) – Nikon D100 (531 800) – Nikon D70 (531 800) – Pentax K10D (531 800) – Nikon D70s (531 800) – Nikon D50 (531 800) – Nikon D40 (531 800) – Panasonic DMC-TZ4 (531 800)

9 Pentax K200D (1874 2800) – Sony DSLR-A300 (1874 2800) – Sony DSLR-A100 (1874 2800) – Nikon D200 (1874 2800) – Sony DSLR-A200 (1874 2800) – Pentax K10D (1874 2800) – Nikon D60 (1874 2800) – Nikon D40X (1874 2800) – Nikon D80 (1874 2800)

9 Pentax Optio WPi (2112 2816) – Panasonic DMC-FX01 (2112 2816) – Fujifilm FinePix F470 (2112 2816) – Sony DSC-T9 (2112 2816) – Sony DSC-S600 (2112 2816) – Sony DSC-W30 (2112 2816) – Pentax Optio W10 (2112 2816) – Sony DSC-H2 (2112 2816) – Sony DSC-W50 (2112 2816)

9 Sony DSC-H5 (1224 1632) – Sony DSC-W100 (1224 1632) – Sony DSC-W30 (1224 1632) – Sony DSC-T10 (1224 1632) – Sony DSC-H2 (1224 1632) – Sony DSC-T50 (1224 1632) – Sony DSC-W70 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)

10 Canon DIGITAL IXUS 40 (768 1024) – Canon PowerShot A70 (768 1024) – Canon PowerShot A300 (768 1024) – Canon PowerShot G2 (768 1024) – Canon PowerShot SD200 (768 1024) – Canon PowerShot A80 (768 1024) – Canon PowerShot A520 (768 1024) – Canon PowerShot S400 (768 1024) – Canon PowerShot A510 (768 1024) – Canon PowerShot S410 (768 1024)

10 Canon DIGITAL IXUS 800 IS (2112 2816) – Canon PowerShot S3 IS (2112 2816) – Canon IXY DIGITAL 800 IS (2112 2816) – Canon PowerShot A540 (2112 2816) – Canon PowerShot G7 (2112 2816) – Canon PowerShot A700 (2112 2816) – Canon DIGITAL IXUS 60 (2112 2816) – Canon PowerShot SD630 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Canon PowerShot SD700 IS (2112 2816)

10 Canon DIGITAL IXUS 860 IS (2448 3264) – Casio EX-S880 (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Ricoh GR Digital (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Olympus E-500 (2448 3264) – Sony DSC-T20 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264)

10 Canon EOS 350D DIGITAL (1866 2800) – Canon EOS 450D (1866 2800) – Sony DSC-H3 (1866 2800) – Canon EOS 30D (1866 2800) – Canon EOS 20D (1866 2800) – Canon EOS 40D (1866 2800) – Canon EOS 400D DIGITAL (1866 2800) – Canon EOS DIGITAL REBEL XSi (1866 2800) – Canon EOS DIGITAL REBEL XT (1866 2800) – Canon EOS DIGITAL REBEL XTi (1866 2800)

10 Canon PowerShot A620 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Panasonic DMC-LS75 (2304 3072) – Sony DSC-T30 (2304 3072) – Olympus SP310 (2304 3072) – Olympus SP550UZ (2304 3072) – Olympus FE230/X790 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Olympus FE240/X795 (2304 3072) – Olympus SP510UZ (2304 3072)

10 Canon PowerShot A700 (2112 2816) – Canon PowerShot A640 (2112 2816) – Canon PowerShot SD880 IS (2112 2816) – Canon DIGITAL IXUS 60 (2112 2816) – Canon PowerShot SD630 (2112 2816) – Canon PowerShot A540 (2112 2816) – Canon PowerShot SD700 IS (2112 2816) – Canon DIGITAL IXUS 800 IS (2112 2816) – Canon PowerShot SD600 (2112 2816) – Canon PowerShot S3 IS (2112 2816)

10 Canon PowerShot SX100 IS (1200 1600) – Nikon E2100 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Canon PowerShot A80 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Nikon E2500 (1200 1600) – Olympus C700UZ (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Canon DIGITAL IXUS 55 (1200 1600) – Canon DIGITAL IXUS 70 (1200 1600)

10 Fujifilm FinePix S1000fd (2736 3648) – Olympus E-520 (2736 3648) – Canon PowerShot G7 (2736 3648) – Panasonic DMC-FZ28 (2736 3648) – Panasonic DMC-FZ50 (2736 3648) – Casio EX-Z1000 (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Olympus E-410 (2736 3648) – Olympus E-400 (2736 3648) – Olympus E-510 (2736 3648)

10 Fujifilm FinePix Z200fd (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Nikon COOLPIX P5000 (2736 3648) – Sony DSC-N2 (2736 3648) – Ricoh G600 (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648) – Nikon COOLPIX S550 (2736 3648)

10 Nikon COOLPIX S7c (2304 3072) – Olympus SP510UZ (2304 3072) – Olympus u770SW,S770SW (2304 3072) – Nikon E7600 (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Olympus FE240/X795 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus SP550UZ (2304 3072) – Olympus FE230/X790 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

10 Nikon D700 (851 1280) – Pentax K100D (851 1280) – Konica Minolta MAXXUM 5D (851 1280) – Nikon D100 (851 1280) – Konica Minolta MAXXUM 7D (851 1280) – Nikon D70s (851 1280) – Canon EOS 400D DIGITAL (851 1280) – Nikon D40 (851 1280) – Nikon D70 (851 1280) – Nikon D50 (851 1280)

10 Sony DSC-P72 (1224 1632) – Sony DSC-W30 (1224 1632) – Sony DSC-H5 (1224 1632) – Sony DSC-W100 (1224 1632) – Sony DSC-W70 (1224 1632) – Sony DSC-T50 (1224 1632) – Sony DSC-T10 (1224 1632) – Sony DSC-H2 (1224 1632) – Sony DSC-W50 (1224 1632) – Sony DSC-W55 (1224 1632)

11 Canon DIGITAL IXUS 860 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot A580 (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264)

11 Canon DIGITAL IXUS 960 IS (768 1024) – Canon PowerShot A2000 IS (768 1024) – Fujifilm FinePix S5700 S700 (768 1024) – Nikon COOLPIX L3 (768 1024) – Pentax Optio M20 (768 1024) – Canon DIGITAL IXUS 60 (768 1024) – Canon PowerShot G9 (768 1024) – Canon PowerShot SD200 (768 1024) – Canon DIGITAL IXUS 40 (768 1024) – Samsung <VLUU L730 / Samsung L730> (768 1024) – Canon PowerShot SX100 IS (768 1024)

11 Canon PowerShot SD1000 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Sony DSC-W55 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus SP510UZ (2304 3072) – Sony DSC-S750 (2304 3072) – Olympus FE240/X795 (2304 3072) – Olympus SP550UZ (2304 3072) – Olympus FE230/X790 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

11 Fujifilm FinePix 3800 (960 1280) – Pentax Optio M30 (960 1280) – Sony DSC-H1 (960 1280) – Sony DSC-P32 (960 1280) – Minolta DiMAGE Z1 (960 1280) – Sony DSC-T100 (960 1280) – Fujifilm FinePix S5000 (960 1280) – Nikon COOLPIX S51 (960 1280) – Canon PowerShot A95 (960 1280) – Vivitar Vivicam 3785 (960 1280) – Panasonic DMC-FZ8 (960 1280)

11 Fujifilm FinePix F650 (2112 2816) – Olympus FE190/X750 (2112 2816) – Fujifilm FinePix F470 (2112 2816) – Olympus SP500UZ (2112 2816) – Sony DSC-H2 (2112 2816) – Sanyo E1 (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Pentax Optio W10 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Casio EX-F1 (2112 2816) – Nikon COOLPIX S3 (2112 2816)

11 Fujifilm FinePix F650 (2112 2816) – Sanyo E6 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Sony DSC-W30 (2112 2816) – Sony DSC-H2 (2112 2816) – Sony DSC-W50 (2112 2816) – Sanyo E1 (2112 2816) – Pentax Optio W10 (2112 2816) – Fujifilm FinePix F470 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S3 (2112 2816)

11 Fujifilm FinePix S5600 (1944 2592) – Canon PowerShot SD450 (1944 2592) – Olympus C5060WZ (1944 2592) – Nikon S1 (1944 2592) – Canon PowerShot SD1000 (1944 2592) – Canon PowerShot SX100 IS (1944 2592) – Nikon E5600 (1944 2592) – Canon PowerShot A530 (1944 2592) – Canon PowerShot SD750 (1944 2592) – Nikon COOLPIX L3 (1944 2592) – Olympus D555Z,C315Z (1944 2592)

11 Fujifilm FinePix S8100fd (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Fujifilm FinePix S1000fd (2736 3648) – Olympus SP570UZ (2736 3648) – Olympus u1000/S1000 (2736 3648) – Canon PowerShot G7 (2736 3648) – Sony DSC-T700 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Sony DSC-T300 (2736 3648) – Sony DSC-W170 (2736 3648) – Sony DSC-N2 (2736 3648)

11 Nikon COOLPIX L2 (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Nikon COOLPIX P80 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-W55 (1536 2048) – Olympus X250,D560Z,C350Z (1536 2048) – Nikon COOLPIX L3 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Nikon E3100 (1536 2048) – Nikon E3200 (1536 2048) – Minolta DiMAGE Z1 (1536 2048)

11 Sony DSC-N1 (768 1024) – Canon PowerShot SD1000 (768 1024) – Sony Ericsson K850i (768 1024) – Sony DSC-H10 (768 1024) – Apple iPhone (768 1024) – Nikon COOLPIX P5100 (768 1024) – Fujifilm FinePix F30 (768 1024) – Olympus C5050Z (768 1024) – Canon PowerShot G9 (768 1024) – Olympus E-520 (768 1024) – Olympus E-3 (768 1024)

11 Sony DSC-S650 (768 1024) – Sony DSC-W5 (768 1024) – Panasonic DMC-FZ8 (768 1024) – Sony DSC-M2 (768 1024) – Canon PowerShot A570 IS (768 1024) – Canon PowerShot S80 (768 1024) – Pentax Optio M20 (768 1024) – Sony DSC-W70 (768 1024) – Canon PowerShot A700 (768 1024) – Sony DSC-T300 (768 1024) – Canon DIGITAL IXUS 60 (768 1024)

12 Canon EOS DIGITAL REBEL XSi (853 1280) – Canon EOS DIGITAL REBEL (853 1280) – Fujifilm FinePix F10 (853 1280) – Canon EOS 30D (853 1280) – Canon EOS 450D (853 1280) – Canon EOS-1D Mark II (853 1280) – Canon EOS 350D DIGITAL (853 1280) – Canon EOS DIGITAL REBEL XTi (853 1280) – Canon EOS 400D DIGITAL (853 1280) – Canon EOS DIGITAL REBEL XT (853 1280) – Canon EOS 40D (853 1280) – Canon EOS 20D (853 1280)

12 Canon PowerShot A590 IS (2448 3264) – Olympus C8080WZ (2448 3264) – Nikon COOLPIX P50 (2448 3264) – Olympus SP350 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Canon PowerShot G9 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Sony DSC-W90 (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Nikon COOLPIX S210 (2448 3264)

12 Canon PowerShot A700 (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Nikon COOLPIX S3 (2112 2816) – Olympus FE190/X750 (2112 2816) – Olympus SP500UZ (2112 2816) – Pentax Optio W10 (2112 2816) – Canon PowerShot A540 (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Sony DSC-W50 (2112 2816)

12 Canon PowerShot SD600 (2112 2816) – Pentax Optio W10 (2112 2816) – Canon PowerShot SD630 (2112 2816) – Sanyo E1 (2112 2816) – Fujifilm FinePix F470 (2112 2816) – Sony DSC-W50 (2112 2816) – Nikon COOLPIX L11 (2112 2816) – Canon PowerShot A540 (2112 2816) – Olympus SP500UZ (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Olympus FE190/X750 (2112 2816) – Canon PowerShot S3 IS (2112 2816)

12 Canon PowerShot SD900 (2736 3648) – Sony DSC-N2 (2736 3648) – Ricoh G600 (2736 3648) – Olympus SP570UZ (2736 3648) – Olympus u1000/S1000 (2736 3648) – Nikon COOLPIX P5000 (2736 3648) – Sony DSC-T700 (2736 3648) – Sony DSC-W170 (2736 3648) – Nikon COOLPIX S550 (2736 3648) – Samsung <KENOX S1050 / Samsung S1050> (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648)

12 Casio EX-Z850 (1200 1600) – Minolta DiMAGE Z1 (1200 1600) – Konica Minolta Camera, Inc. DiMAGE Z2 (1200 1600) – Konica Minolta DiMAGE Z10 (1200 1600) – Canon PowerShot G9 (1200 1600) – Nikon E950 (1200 1600) – Nikon E2100 (1200 1600) – Nikon E775 (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Sony CYBERSHOT (1200 1600) – Konica Minolta DiMAGE X50 (1200 1600) – Canon PowerShot S200 (1200 1600)

12 Nikon COOLPIX S6 (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Vivitar ViviCam 6324 (2112 2816) – Sony DSC-S600 (2112 2816) – Sony DSC-T9 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Sony DSC-H2 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Sony DSC-W30 (2112 2816) – Pentax Optio W10 (2112 2816) – Sony DSC-W50 (2112 2816) – Digital Camera 6MP-9FW (2112 2816)

12 Nikon COOLPIX S6 (2112 2816) – Sony DSC-H2 (2112 2816) – Vivitar ViviCam 5388 (2112 2816) – Canon PowerShot S3 IS (2112 2816) – Digital Camera 6MP-9FW (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Panasonic DMC-FZ7 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Olympus X-3,C-60Z (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Sanyo VPC-S600 (2112 2816)

12 Nikon E7600 (2304 3072) – Olympus SP510UZ (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Sony DSC-W80 (2304 3072) – Olympus FE240/X795 (2304 3072) – Pentax Optio W30 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus SP550UZ (2304 3072) – Olympus FE230/X790 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

12 Nikon E7600 (2304 3072) – Olympus u760,S760 (2304 3072) – Olympus FE240/X795 (2304 3072) – Sony DSC-W120 (2304 3072) – Olympus SP550UZ (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-W55 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Fujifilm FinePix Z10fd (2304 3072) – Olympus FE230/X790 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

12 Samsung VLUU NV10, NV10 (2736 3648) – Fujifilm FinePix S8100fd (2736 3648) – Olympus SP570UZ (2736 3648) – Sony DSC-T700 (2736 3648) – Ricoh G600 (2736 3648) – Nikon COOLPIX P5000 (2736 3648) – Sony DSC-W170 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Nikon COOLPIX S550 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648) – Fujifilm FinePix S2000HD (2736 3648)

12 Sony DSC-H2 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Pentax Optio W10 (2112 2816) – Sony DSC-W30 (2112 2816) – Pentax Optio WPi (2112 2816) – Sanyo E1 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Olympus FE190/X750 (2112 2816) – Olympus SP500UZ (2112 2816) – Nikon COOLPIX S3 (2112 2816) – Olympus FE-120,X-700 (2112 2816)

12 Sony DSC-N1 (480 640) – Sony DSC-T9 (480 640) – Sony DSC-P72 (480 640) – Sony DSC-W50 (480 640) – Sony MVC-CD500 (480 640) – Sony CYBERSHOT (480 640) – Sony DSC-W35 (480 640) – Sony DSC-P32 (480 640) – Sony DSC-T5 (480 640) – Sony DSC-W55 (480 640) – Sony DSC-L1 (480 640) – Sony DCR-HC32E (480 640)

12 Sony DSC-P120 (1944 2592) – Sony DSC-M1 (1944 2592) – Sony DSC-T77 (1944 2592) – Sony DSC-P93A (1944 2592) – Sony DSC-F828 (1944 2592) – Sony DSC-W1 (1944 2592) – Sony DSC-V1 (1944 2592) – Sony DSC-P10 (1944 2592) – Sony DSC-P100 (1944 2592) – Sony DSC-P92 (1944 2592) – Sony DSC-P93 (1944 2592) – Sony DSC-T1 (1944 2592)

12 Sony DSC-P92 (960 1280) – Sony DSC-W7 (960 1280) – Sony DSC-P150 (960 1280) – Sony DSC-W12 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P200 (960 1280) – Sony DSC-T9 (960 1280) – Sony DSC-P10 (960 1280) – Sony DSC-H1 (960 1280) – Olympus E-510 (960 1280) – Panasonic DMC-TZ3 (960 1280) – Sony DSC-W5 (960 1280)

13 Canon DIGITAL IXUS 860 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot G9 (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot A650 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon PowerShot S80 (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264)

- 13 Canon IXY DIGITAL 820 IS (2736 3648) – Canon PowerShot SD890 IS (2736 3648) – Canon PowerShot SD880 IS (2736 3648) – Canon PowerShot A1000 IS (2736 3648) – Canon DIGITAL IXUS 900Ti (2736 3648) – Canon PowerShot SD770 IS (2736 3648) – Canon DIGITAL IXUS 90 IS (2736 3648) – Canon DIGITAL IXUS 85 IS (2736 3648) – Canon DIGITAL IXUS 970 IS (2736 3648) – Canon PowerShot SD790 IS (2736 3648) – Canon PowerShot A640 (2736 3648) – Canon PowerShot SD900 (2736 3648) – Canon PowerShot G7 (2736 3648)
- 13 Canon PowerShot A470 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Olympus u710,S710 (2304 3072) – Sony DSC-W70 (2304 3072) – Canon PowerShot A620 (2304 3072) – Fujifilm FinePix Z10fd (2304 3072) – Sony DSC-P200 (2304 3072) – Sony DSC-S650 (2304 3072) – Casio EX-Z12 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Casio EX-S770 (2304 3072) – Sony DSC-W35 (2304 3072)
- 13 Canon PowerShot A570 IS (1200 1600) – Nikon E5000 (1200 1600) – Sanyo VPC-T700 (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Canon PowerShot SD630 (1200 1600) – Casio EX-Z850 (1200 1600) – Canon PowerShot SD200 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Nikon E2100 (1200 1600) – Konica Minolta DiMAGE X50 (1200 1600) – HTC Hermes (1200 1600) – Samsung Digimax 301 (1200 1600)
- 13 Canon PowerShot S5 IS (600 800) – Canon DIGITAL IXUS 70 (600 800) – Canon PowerShot SD790 IS (600 800) – Sony DSC-S500 (600 800) – Fujifilm FinePix S5600 (600 800) – Olympus E-400 (600 800) – Nikon E8700 (600 800) – Olympus E-500 (600 800) – Sony DSC-T70 (600 800) – Nikon E7600 (600 800) – Canon PowerShot SX100 IS (600 800) – Nikon E995 (600 800) – Kodak EASYSHARE Z1012 IS Digital Camera (600 800)
- 13 Casio EX-Z100 (2736 3648) – Nikon COOLPIX S60 (2736 3648) – Olympus SP570UZ (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Sony DSC-W170 (2736 3648) – Casio EX-Z1050 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Ricoh G600 (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Nikon COOLPIX P5000 (2736 3648) – Nikon COOLPIX S550 (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Sony DSC-T300 (2736 3648)
- 13 Fujifilm FinePix A345 (1066 1600) – Canon EOS DIGITAL REBEL XSi (1066 1600) – Canon EOS 30D (1066 1600) – Canon EOS 50D (1066 1600) – Canon EOS 20D (1066 1600) – Canon EOS DIGITAL REBEL (1066 1600) – Samsung Samsung S85 (1066 1600) – Canon EOS 40D (1066 1600) – Canon EOS 40D (1066 1600) – Pentax \*ist DS (1066 1600) – Canon EOS 350D DIGITAL (1066 1600) – Canon EOS 400D DIGITAL (1066 1600) – Canon EOS DIGITAL REBEL XT (1066 1600) – Canon EOS DIGITAL REBEL XTi (1066 1600)
- 13 Fujifilm FinePix S5700 S700 (768 1024) – Nikon COOLPIX L3 (768 1024) – Olympus SP510UZ (768 1024) – Olympus C2Z,D520Z,C220Z (768 1024) – Canon PowerShot S3 IS (768 1024) – Canon PowerShot SD600 (768 1024) – Hewlett-Packard HP Photosmart M437 (768 1024) – Olympus C5060WZ (768 1024) – Casio EX-Z1000 (768 1024) – Fujifilm FinePix F700 (768 1024) – Canon PowerShot A710 IS (768 1024) – Olympus E-500 (768 1024) – Sony DSC-H1 (768 1024)
- 13 Nikon COOLPIX P50 (1536 2048) – Olympus C3040Z (1536 2048) – Olympus C3100Z,C3020Z (1536 2048) – Nikon E885 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Nikon COOLPIX P80 (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Nikon E3100 (1536 2048) – Nikon COOLPIX L3 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Olympus C740UZ (1536 2048) – Nikon E3200 (1536 2048) – Nikon E7600 (1536 2048)
- 13 Nikon E3700 (1536 2048) – Sony DSC-W55 (1536 2048) – Sanyo J1 (1536 2048) – Sony DSC-H7 (1536 2048) – Hewlett-Packard hp photosmart 720 (1536 2048) – Olympus SP550UZ (1536 2048) – Sony Ericsson K800i (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Nikon E3100 (1536 2048) – Sony DSC-H9 (1536 2048) – Nikon E885 (1536 2048) – Nikon E3200 (1536 2048) – Nikon COOLPIX S600 (1536 2048)
- 13 Panasonic DMC-FX35 (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Canon PowerShot SD790 IS (2736 3648) – Nikon COOLPIX P80 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Olympus SP570UZ (2736 3648) – Fujifilm FinePix Z20fd (2736 3648) – Sony DSC-T300 (2736 3648) – Olympus E-410 (2736 3648) – Panasonic DMC-FX500 (2736 3648) – Nikon COOLPIX S550 (2736 3648) – Fujifilm FinePix S1000fd (2736 3648) – Panasonic DMC-FZ28 (2736 3648)
- 13 Panasonic DMC-FZ50 (1365 2048) – Fujifilm FinePix S9100 (1365 2048) – Canon EOS 450D (1365 2048) – Canon EOS 20D (1365 2048) – Canon EOS 50D (1365 2048) – Sony DSC-R1 (1365 2048) – Canon EOS 10D (1365 2048) – Canon EOS 30D (1365 2048) – Canon EOS DIGITAL REBEL XSi (1365 2048) – Sony DSLR-A700 (1365 2048) – Canon EOS DIGITAL REBEL XTi (1365 2048) – Canon EOS 400D DIGITAL (1365 2048) – Canon EOS 40D (1365 2048)
- 13 Samsung NV11, VLUU NV11 (2736 3648) – Sony DSC-T300 (2736 3648) – Casio EX-Z1000 (2736 3648) – Casio EX-Z1050 (2736 3648) – Samsung VLUU NV10, NV10 (2736 3648) – Olympus u1000/S1000 (2736 3648) – Sony DSC-T700 (2736 3648) – Samsung NV15, VLUU NV15 (2736 3648) – Olympus u1010,S1010 (2736 3648) – Panasonic DMC-FZ50 (1365 2048) – Olympus E-3 (2736 3648) – Samsung NV24HD, VLUU NV24HD, LANDIAO NV106HD (2736 3648) – Sony DSC-N2 (2736 3648)
- 14 Canon DIGITAL IXUS 60 (1200 1600) – Canon PowerShot S30 (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot S50 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot A200 (1200 1600) – Canon PowerShot A700 (1200 1600) – Canon PowerShot G9 (1200 1600) – Canon PowerShot A40 (1200 1600) – Canon PowerShot A560 (1200 1600)
- 14 Canon EOS 40D (533 800) – Canon EOS DIGITAL REBEL XSi (533 800) – Sony DSLR-A700 (533 800) – Canon EOS-1D Mark II (533 800) – Canon EOS 20D (533 800) – Canon EOS 450D (533 800) – Canon EOS 10D (533 800) – Canon EOS 300D DIGITAL (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XT (533 800) – Canon EOS 350D DIGITAL (533 800) – Canon EOS DIGITAL REBEL (533 800) – Canon EOS 30D (533 800) – Canon EOS DIGITAL REBEL XTi (533 800)
- 14 Canon EOS D30 (1365 2048) – Casio EX-S770 (1365 2048) – Canon EOS 300D DIGITAL (1365 2048) – Canon EOS 5D (1365 2048) – Canon EOS 20D (1365 2048) – Canon EOS 40D (1365 2048) – Canon EOS DIGITAL REBEL XTi (1365 2048) – Canon EOS DIGITAL REBEL (1365 2048) – Canon EOS 350D DIGITAL (1365 2048) – Canon EOS DIGITAL REBEL XSi (1365 2048) – Canon EOS 30D (1365 2048) – Canon EOS DIGITAL REBEL XT (1365 2048) – Canon EOS-1D Mark III (1365 2048) – Canon EOS 400D DIGITAL (1365 2048)
- 14 Canon EOS Kiss X2 (1067 1600) – Canon EOS 300D DIGITAL (1067 1600) – Canon EOS 5D (1067 1600) – Canon EOS 20D (1067 1600) – Canon EOS 10D (1067 1600) – Canon EOS 350D DIGITAL (1067 1600) – Canon EOS 450D (1067 1600) – Fujifilm FinePix F20 (1067 1600) – Canon EOS 400D DIGITAL (1067 1600) – Canon EOS DIGITAL REBEL XT (1067 1600) – Canon EOS DIGITAL REBEL XSi (1067 1600) – Canon EOS DIGITAL REBEL XTi (1067 1600) – Canon EOS 40D (1067 1600) – Canon EOS 30D (1067 1600)
- 14 Canon PowerShot A1000 IS (2736 3648) – Canon DIGITAL IXUS 870 IS (2736 3648) – Canon DIGITAL IXUS 970 IS (2736 3648) – Canon PowerShot SD880 IS (2736 3648) – Canon DIGITAL IXUS 900Ti (2736 3648) – Canon PowerShot SD890 IS (2736 3648) – Canon DIGITAL IXUS 90 IS (2736 3648) – Canon DIGITAL IXUS 85 IS (2736 3648) – Canon PowerShot SD900 (2736 3648) – Canon PowerShot SD770 IS (2736 3648) – Canon PowerShot SX10 IS (2736 3648) – Canon PowerShot SD790 IS (2736 3648) – Canon PowerShot G7 (2736 3648) – Canon PowerShot A640 (2736 3648)
- 14 Canon PowerShot S80 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon DIGITAL IXUS 950 IS (2448 3264) – Canon PowerShot SD950 IS (2448 3264) – Canon PowerShot G9 (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon PowerShot A580 (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264)
- 14 Canon PowerShot SD400 (768 1024) – Samsung NV11, VLUU NV11 (768 1024) – Canon DIGITAL IXUS 90 IS (768 1024) – Panasonic DMC-FZ18 (768 1024) – Pentax Optio S5i (768 1024) – Canon PowerShot S20 (768 1024) – Apple iPhone (768 1024) – Panasonic DMC-FX30 (768 1024) – Olympus E-510 (768 1024) – Canon PowerShot G9 (768 1024) – Panasonic DMC-FZ4 (768 1024) – Panasonic DMC-FZ8 (768 1024) – Ricoh Caplio GX100 (768 1024) – Nikon COOLPIX P80 (768 1024)
- 14 Casio EX-Z75 (480 640) – Sony DSC-P200 (480 640) – Sony Ericsson K800i (480 640) – Nikon COOLPIX S9 (480 640) – Canon PowerShot Pro1 (480 640) – Casio EX-Z60 (480 640) – Nikon COOLPIX S200 (480 640) – Olympus FE240/X795 (480 640) – Canon PowerShot S3 IS (480 640) – Casio EX-Z600 (480 640) – Sony DSC-P32 (480 640) – Ricoh Caplio GX100 (480 640) – Canon PowerShot G9 (480 640) – Panasonic DMC-FZ20 (480 640)
- 14 Olympus C8080WZ (2448 3264) – Sony DSC-W150 (2448 3264) – Samsung Pro 815 (2448 3264) – Sony DSC-T70 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-H10 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-N2 (2448 3264) – Sony DSC-N2 (2448 3264) – Sony DSC-N1 (2448 3264) – Sony DSC-W100 (2448 3264) – Samsung NV8, VLUU NV8 (2448 3264) – Olympus E-500 (2448 3264)
- 14 Olympus FE320,X835,C540 (2448 3264) – Sony DSC-W100 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-H3 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-H9 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-T100 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-T70 (2448 3264) – Sony DSC-W90 (2448 3264)
- 14 Sony CD MAVICA (1536 2048) – Sony DSC-P73 (1536 2048) – Sony DSC-P120 (1536 2048) – Sony DSC-T20 (1536 2048) – Sony DSC-P32 (1536 2048) – Sony DSC-P100 (1536 2048) – Sony DSC-T1 (1536 2048) – Sony DSC-P93 (1536 2048) – Sony DSC-P10 (1536 2048) – Sony DSC-P8 (1536 2048) – Sony DSC-P72 (1536 2048) – Sony DSC-V1 (1536 2048) – Sony CYBERSHOT (1536 2048) – Sony DSC-W1 (1536 2048)
- 14 Sony DSC-P100 (480 640) – Sony DSC-W100 (480 640) – Sony MVC-CD500 (480 640) – Sony DSC-P41 (480 640) – Sony DSC-W120 (480 640) – Sony DSC-W35 (480 640) – Sony CYBERSHOT (480 640) – Sony DSC-T5 (480 640) – Sony DSC-T9 (480 640) – Sony DSC-P73 (480 640) – Canon PowerShot SX10 IS (480 640) – Sony DSC-T1 (480 640) – Sony DSC-L1 (480 640) – Sony DSC-W55 (480 640)
- 14 Sony DSC-T10 (2304 3072) – Sony DSC-W17 (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-W70 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Sony DSC-W120 (2304 3072) – Pentax Optio M20 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W55 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Sony DSC-W80 (2304 3072)
- 15 Canon DIGITAL IXUS 750 (2304 3072) – Canon IXY DIGITAL 600 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon DIGITAL IXUS 75 (2304 3072) – Canon PowerShot A550 (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon PowerShot A470 (2304 3072) – Canon PowerShot SD550 (2304 3072) – Canon DIGITAL IXUS 850 IS (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Canon PowerShot SD750 (2304 3072)
- 15 Canon DIGITAL IXUS 75 (2304 3072) – Canon PowerShot S70 (2304 3072) – Canon PowerShot G6 (2304 3072) – Canon PowerShot A550 (2304 3072) – Canon DIGITAL IXUS 75 (2304 3072) – Canon DIGITAL IXUS 850 IS (2304 3072) – Canon PowerShot SD550 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon PowerShot SD750 (2304 3072) – Canon PowerShot SD1000 (2304 3072)
- 15 Canon DIGITAL IXUS 850 IS (2304 3072) – Canon IXY DIGITAL 600 (2304 3072) – Canon DIGITAL IXUS 700 (2304 3072) – Canon DIGITAL IXUS 75 (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot SD500 (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot A550 (2304 3072) – Canon PowerShot SD550 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Canon PowerShot A560 (2304 3072)
- 15 Canon PowerShot A620 (600 800) – Canon PowerShot A720 IS (600 800) – Canon PowerShot SX100 IS (600 800) – Casio EX-Z850 (600 800) – Olympus X600,D630,FE5500 (600 800) – Casio EX-Z40 (600 800) – Nikon COOLPIX S210 (600 800) – Canon DIGITAL IXUS 70 (600 800) – Olympus u1030SW,S1030SW (600 800) – Canon PowerShot S2 IS (600 800) – Canon PowerShot S5 IS (600 800) – Canon PowerShot SD1000 (600 800) – Olympus SP560UZ (600 800) – Minolta DiMAGE Z1 (600 800) – Canon PowerShot SD750 (600 800)

15 Canon PowerShot S3 IS (480 640) – Canon PowerShot SD1000 (480 640) – Canon PowerShot A560 (480 640) – Canon PowerShot A590 IS (480 640) – Canon PowerShot A570 IS (480 640) – Sony DSC-W80 (480 640) – Canon PowerShot SX110 IS (480 640) – Palm Centro (480 640) – Treo 755p (480 640) – Canon PowerShot A580 (480 640) – Canon PowerShot A720 IS (480 640) – Treo 680 (480 640) – Olympus uD800,S800 (480 640) – Sony DSC-W55 (480 640) – Leica C-LUX 2 (480 640)

15 Casio EX-Z1080 (480 640) – Nikon COOLPIX S50c (480 640) – Nikon E7600 (480 640) – Sony DSC-H10 (480 640) – HTC TITA100 (480 640) – Canon DIGITAL IXUS 55 (480 640) – Canon PowerShot G9 (480 640) – Fujifilm FinePix A205 (480 640) – Canon PowerShot S3 IS (480 640) – Sony Ericsson W810i (480 640) – HTC HTC.P4350 (480 640) – Olympus FE280,X820,C520 (480 640) – Canon PowerShot A610 (480 640) – Research In Motion BlackBerry 8100 SERIES (480 640) – Sony DSC-T9 (480 640) – Casio EX-Z700 (1536 2048) – Fujifilm FinePix S5200 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Olympus u770SW,S770SW (1536 2048) – Pentax Optio S (1536 2048) – Sony CYBERSHOT (1536 2048) – Nikon E3100 (1536 2048) – Olympus X250,D560Z,C350Z (1536 2048) – Panasonic DMC-FZ18 (1536 2048) – Sony Ericsson K800i (1536 2048) – Casio EX-Z70 (1536 2048) – Casio EX-Z75 (1536 2048) – Sony DSC-W1 (1536 2048) – Casio EX-Z1000 (1536 2048) – Casio EX-Z60 (1536 2048)

15 Nikon COOLPIX L3 (1536 2048) – Nikon E3700 (1536 2048) – Nikon E990 (1536 2048) – Olympus C3100Z,C3020Z (1536 2048) – Sanyo J1 (1536 2048) – Sony DSC-T200 (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Nikon E3100 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-W80 (1536 2048) – Nikon E885 (1536 2048) – Nikon E3200 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-H9 (1536 2048) – Sony DSC-H7 (1536 2048)

15 Sony DSC-T9 (2112 2816) – Casio EX-Z850 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Panasonic DMC-FZ7 (2112 2816) – Nikon COOLPIX L11 (2112 2816) – Olympus FE170,X760 (2112 2816) – Canon PowerShot S3 IS (2112 2816) – Casio EX-Z110 (2112 2816) – Olympus SP500UZ (2112 2816) – Canon DIGITAL IXUS 800 IS (2112 2816) – Canon PowerShot A540 (2112 2816) – Casio EX-Z600 (2112 2816) – Casio EX-S600 (2112 2816) – Canon PowerShot SD630 (2112 2816) – Casio EX-Z60 (2112 2816)

15 Sony DSC-W7 (1944 2592) – Sony DSC-T20 (1944 2592) – Sony DSC-W90 (1944 2592) – Nikon E5400 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-W200 (1944 2592) – Nikon E5900 (1944 2592) – Canon PowerShot A530 (1944 2592) – Sony DSC-T70 (1944 2592) – Nikon S1 (1944 2592) – Nikon COOLPIX L3 (1944 2592) – Canon PowerShot A95 (1944 2592) – Nikon E5600 (1944 2592) – Sony DSC-W80 (1944 2592)

16 Canon DIGITAL IXUS 85 IS (2112 2816) – Canon IXY DIGITAL 80 (2112 2816) – Canon PowerShot SD790 IS (2112 2816) – Canon PowerShot SD880 IS (2112 2816) – Canon PowerShot G7 (2112 2816) – Canon DIGITAL IXUS 65 (2112 2816) – Canon PowerShot SX110 IS (2112 2816) – Canon DIGITAL IXUS 800 IS (2112 2816) – Canon PowerShot A700 (2112 2816) – Canon DIGITAL IXUS 60 (2112 2816) – Canon DIGITAL IXUS 90 IS (2112 2816) – Canon PowerShot SD700 IS (2112 2816) – Canon PowerShot SD630 (2112 2816) – Canon PowerShot A540 (2112 2816) – Canon PowerShot S3 IS (2112 2816) – Canon PowerShot SD600 (2112 2816)

16 Canon PowerShot G3 (600 800) – Fujifilm FinePix S5700 S700 (600 800) – Fujifilm FinePix S8000fd (600 800) – Nikon COOLPIX S9 (600 800) – Olympus u1000/S1000 (600 800) – Canon PowerShot A540 (600 800) – Casio EX-Z75 (600 800) – Nikon E995 (600 800) – Canon PowerShot A430 (600 800) – Nikon COOLPIX S210 (600 800) – Canon PowerShot A620 (600 800) – Nikon COOLPIX S52c (600 800) – Canon PowerShot G7 (600 800) – Sony DSC-H1 (600 800) – Canon DIGITAL IXUS 60 (600 800) – Nikon D70 (600 800)

16 Canon PowerShot SD450 (1536 2048) – Canon DIGITAL IXUS 950 IS (1536 2048) – Canon IXY DIGITAL 910 IS (1536 2048) – Canon PowerShot A400 (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot SD870 IS (1536 2048) – Canon PowerShot A610 (1536 2048) – Canon PowerShot A70 (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Canon DIGITAL IXUS 50 (1536 2048) – Canon PowerShot SD850 IS (1536 2048) – Canon PowerShot S230 (1536 2048) – Canon PowerShot SD750 (1536 2048) – Canon PowerShot SD1000 (1536 2048)

17 Canon DIGITAL IXUS 60 (768 1024) – Canon PowerShot SD1000 (768 1024) – Canon PowerShot SD700 IS (768 1024) – Olympus E-500 (768 1024) – Sony DSC-T50 (768 1024) – Canon PowerShot S5 IS (768 1024) – Nikon COOLPIX L3 (768 1024) – Panasonic DMC-TZ2 (768 1024) – Nikon COOLPIX L18 (768 1024) – Canon PowerShot SD870 IS (768 1024) – Panasonic DMC-FZ8 (768 1024) – Canon IXY DIGITAL 80 (768 1024) – Olympus C5050Z (768 1024) – Fujifilm FinePix A820 (768 1024) – Canon PowerShot A650 IS (768 1024) – Sanyo VPC-T700 (768 1024) – Sony DSC-P92 (768 1024)

17 Canon DIGITAL IXUS 900Ti (2112 2816) – Canon PowerShot SD880 IS (2112 2816) – Canon PowerShot SX110 IS (2112 2816) – Canon PowerShot SD790 IS (2112 2816) – Canon IXY DIGITAL 800 IS (2112 2816) – Canon PowerShot SD900 (2112 2816) – Canon DIGITAL IXUS 65 (2112 2816) – Canon PowerShot A700 (2112 2816) – Canon PowerShot A640 (2112 2816) – Canon DIGITAL IXUS 60 (2112 2816) – Canon PowerShot G7 (2112 2816) – Canon PowerShot A540 (2112 2816) – Canon DIGITAL IXUS 800 IS (2112 2816) – Canon PowerShot SD630 (2112 2816) – Canon PowerShot SD700 IS (2112 2816) – Canon PowerShot SD600 (2112 2816) – Canon PowerShot S3 IS (2112 2816)

17 Canon PowerShot G2 (768 1024) – Canon PowerShot S1 IS (768 1024) – Canon PowerShot S45 (768 1024) – Canon PowerShot A40 (768 1024) – Canon PowerShot A60 (768 1024) – Canon PowerShot A510 (768 1024) – Canon PowerShot SD200 (768 1024) – Canon PowerShot A85 (768 1024) – Canon PowerShot S200 (768 1024) – Canon PowerShot S410 (768 1024) – Canon PowerShot A400 (768 1024) – Canon PowerShot A430 (768 1024) – Canon PowerShot A20 (768 1024) – Canon PowerShot S110 (768 1024) – Canon PowerShot A80 (768 1024) – Canon PowerShot A520 (768 1024) – Canon PowerShot A70 (768 1024)

17 Casio EX-S600 (2112 2816) – Panasonic DMC-FX01 (2112 2816) – Pentax Optio WPi (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Olympus FE190/X750 (2112 2816) – Panasonic DMC-FZ7 (2112 2816) – Nikon COOLPIX L2 (2112 2816) – Nikon COOLPIX S5 (2112 2816) – Nikon COOLPIX S6 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Sony DSC-S600 (2112 2816) – Sony DSC-T9 (2112 2816) – Sony DSC-W30 (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Pentax Optio W10 (2112 2816) – Sony DSC-H2 (2112 2816) – Sony DSC-W50 (2112 2816)

17 Konica Minolta Camera, Inc. DiMAGE Xg (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Nikon E3100 (1536 2048) – Nikon E995 (1536 2048) – Sony DSC-W90 (1536 2048) – Canon PowerShot S230 (1536 2048) – Olympus C3100Z,C3020Z (1536 2048) – Sony DSC-H2 (1536 2048) – Sony DSC-W55 (1536 2048) – Nikon E3200 (1536 2048) – Sony DSC-T100 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-W80 (1536 2048) – Sony DSC-H9 (1536 2048) – Nikon COOLPIX P5100 (1536 2048) – Sony DSC-H7 (1536 2048)

17 Nikon E5200 (1944 2592) – Sony DSC-H3 (1944 2592) – Sony DSC-H7 (1944 2592) – Sony DSC-T7 (1944 2592) – Sony DSC-W200 (1944 2592) – Sony DSC-P200 (1944 2592) – Sony DSC-W1 (1944 2592) – Sony DSC-W90 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-W7 (1944 2592) – Sony DSC-F828 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-T20 (1944 2592) – Sony DSC-H9 (1944 2592) – Sony DSC-W80 (1944 2592) – Sony DSC-T90 (1944 2592)

17 Nikon E7900 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Nikon E7600 (2304 3072) – Olympus SP510UZ (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Olympus FE240/X795 (2304 3072) – Pentax Optio W30 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Olympus SP550UZ (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Olympus FE230/X790 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

17 Pentax K100D (533 800) – Sony DSC-S700 (533 800) – Canon EOS-1Ds Mark II (533 800) – Canon EOS 450D (533 800) – Canon EOS 10D (533 800) – Canon EOS DIGITAL REBEL XSi (533 800) – Panasonic DMC-FZ8 (533 800) – Canon EOS 20D (533 800) – Canon EOS 30D (533 800) – Canon EOS-1D Mark II N (533 800) – Canon EOS 5D (533 800) – Canon EOS DIGITAL REBEL (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XT (533 800) – Canon EOS 350D DIGITAL (533 800) – Canon EOS 40D (533 800) – Canon EOS DIGITAL REBEL XTi (533 800)

18 Canon DIGITAL IXUS 65 (2112 2816) – Canon DIGITAL IXUS 800 IS (2112 2816) – Olympus FE-120,X-700 (2112 2816) – Canon PowerShot A700 (2112 2816) – Sanyo E6 (2112 2816) – Nikon COOLPIX S4 (2112 2816) – Sony DSC-W30 (2112 2816) – Sony DSC-H2 (2112 2816) – Canon PowerShot S3 IS (2112 2816) – Canon PowerShot SD700 IS (2112 2816) – Nikon COOLPIX S10 (2112 2816) – Nikon COOLPIX L6 (2112 2816) – Canon PowerShot SD600 (2112 2816) – Pentax Optio W10 (2112 2816) – Fujifilm FinePix F470 (2112 2816) – Sony DSC-W50 (2112 2816) – Nikon COOLPIX S3 (2112 2816) – Samsung <KENOX S630 / Samsung S630> (2112 2816)

18 Canon EOS 5D (853 1280) – Canon EOS 450D (853 1280) – Panasonic DMC-TZ5 (853 1280) – Sony DSC-P200 (853 1280) – Canon EOS 300D DIGITAL (853 1280) – Panasonic DMC-TZ3 (853 1280) – Sony DSC-W55 (853 1280) – Canon EOS DIGITAL REBEL XSi (853 1280) – Canon EOS D30 (853 1280) – Canon EOS DIGITAL REBEL (853 1280) – Canon EOS 20D (853 1280) – Canon EOS 400D DIGITAL (853 1280) – Canon EOS 40D (853 1280) – Pentax K100D (853 1280) – Canon EOS DIGITAL REBEL XT (853 1280) – Canon EOS 350D DIGITAL (853 1280) – Canon EOS 30D (853 1280) – Canon EOS DIGITAL REBEL XTi (853 1280)

18 Canon IXY DIGITAL 910 IS (2448 3264) – Canon PowerShot S80 (2448 3264) – Canon PowerShot Pro1 (2448 3264) – Canon PowerShot SD950 IS (2448 3264) – Canon DIGITAL IXUS 950 IS (2448 3264) – Canon DIGITAL IXUS 960 IS (2448 3264) – Canon PowerShot G9 (2448 3264) – Canon DIGITAL IXUS 860 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon PowerShot A580 (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264)

18 Canon PowerShot A530 (1536 2048) – Canon PowerShot S230 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Canon PowerShot SD450 (1536 2048) – Canon PowerShot SD750 (1536 2048) – Canon PowerShot S500 (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Canon PowerShot A70 (1536 2048) – Canon PowerShot A720 IS (1536 2048) – Canon DIGITAL IXUS 70 (1536 2048) – Canon PowerShot A75 (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Canon PowerShot SD200 (1536 2048) – Canon PowerShot A400 (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot A95 (1536 2048)

18 Canon PowerShot S100 (480 640) – Nokia N96 (480 640) – T-Mobile Dash T-Mobile Dash (480 640) – Fujifilm FinePix40i (480 640) – T-Mobile(R) Sidekick LX (480 640) – Olympus C160,D395 (480 640) – Sony DSC-T100 (480 640) – Sony DSC-T10 (480 640) – Sony CYBERSHOT (480 640) – Sony Ericsson K750i (480 640) – Canon PowerShot A470 (480 640) – Canon PowerShot S400 (480 640) – Canon PowerShot A460 (480 640) – Olympus FE310,X840,C530 (480 640) – Canon PowerShot A590 IS (480 640) – Casio EX-Z60 (480 640) – Panasonic DMC-LZ8 (480 640) – Sony Ericsson K800i (480 640)

18 Canon PowerShot S70 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Panasonic DMC-FZ8 (2304 3072) – Canon PowerShot G6 (2304 3072) – Sony DSC-P200 (2304 3072) – Canon IXY DIGITAL 10 (2304 3072) – Olympus FE210,X775 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Sony DSC-W55 (2304 3072) – Panasonic DMC-TZ3 (2304 3072) – Olympus u720SW,S720SW (2304 3072) – Casio EX-Z75 (2304 3072) – Casio EX-Z700 (2304 3072) – Casio EX-Z750 (2304 3072) – Casio EX-S770 (2304 3072) – Casio EX-Z70 (2304 3072)

18 Canon PowerShot SD850 IS (2448 3264) – Fujifilm FinePix J10 (2448 3264) – Nikon COOLPIX L18 (2448 3264) – Panasonic DMC-LS80 (2448 3264) – Canon DIGITAL IXUS 950 IS (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Canon PowerShot SD870 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon PowerShot A630 (2448 3264) – Casio EX-Z850 (2448 3264) – Panasonic DMC-FZ18 (2448 3264) – Sony DSC-W150 (2448 3264) – Olympus E-300 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Olympus E-500 (2448 3264)

18 Sony DSC-T70 (2448 3264) – Olympus u820,S820 (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-H9 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264) – Olympus SP350 (2448 3264) – Olympus SP560UZ (2448 3264) – Pentax Optio Lx0 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-T100 (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Olympus C8080WZ (2448 3264) – Olympus FE280,X820,C520 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Fujifilm FinePix Z100fd (2448 3264) – Sony DSC-W90 (2448 3264)

19 Fujifilm FinePix F47fd (533 800) – Canon EOS 5D (533 800) – Canon EOS 450D (533 800) – Fujifilm FinePix A700 (533 800) – Canon EOS 30D (533 800) – Canon EOS-1D Mark III (533 800) – Canon EOS 20D (533 800) – Sony DSC-T100 (533 800) – Canon EOS DIGITAL REBEL XSi (533 800) – Sony DSC-W70 (533 800) – Canon EOS 400D DIGITAL (533 800) – Canon EOS 350D DIGITAL (533 800) – Canon EOS DIGITAL REBEL XT (533 800) – Panasonic DMC-FZ18 (533 800) – Olympus SP550UZ (533 800) – Sony DSLR-A100 (533 800) – Canon EOS DIGITAL REBEL (533 800) – Canon EOS 40D (533 800) – Canon EOS DIGITAL REBEL XT (533 800)

19 Hewlett-Packard hp photosmart 720 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Sanyo J1 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Olympus C3100Z,C3020Z (1536 2048) – Nikon COOLPIX S600 (1536 2048) – Olympus X250,D560Z,C350Z (1536 2048) – Sony DSC-H9 (1536 2048) – Minolta DiMAGE Xt (1536 2048) – Olympus C740UZ (1536 2048) – Nikon E3100 (1536 2048) – Nikon E7600 (1536 2048) – Canon PowerShot A460 (1536 2048) – Canon DIGITAL IXUS 500 (1536 2048) – Olympus C740UZ (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Nikon E3200 (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot G9 (1536 2048)

19 Sony DSC-F32 (960 1280) – Sony DSC-T5 (960 1280) – Sony DSC-W7 (960 1280) – Sony DSC-P52 (960 1280) – Sony DSC-T3 (960 1280) – Sony DSC-S90 (960 1280) – Sony DSC-T33 (960 1280) – Panasonic DMC-TZ3 (960 1280) – Sony DSC-P150 (960 1280) – Sony DSC-P92 (960 1280) – Sony DSC-P92 (960 1280) – Sony FDMAVICA (960 1280) – Sony DSC-P200 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P10 (960 1280) – Sony DSC-H1 (960 1280) – Canon DIGITAL IXUS 40 (960 1280) – Sony DSC-W5 (960 1280) – Olympus E-510 (960 1280)

19 Sony DSC-P92 (960 1280) – Sony DSC-S40 (960 1280) – Sony DSC-S90 (960 1280) – Sony DSC-T7 (960 1280) – Sony DSC-W12 (960 1280) – Sony DSC-P41 (960 1280) – Minolta DiMAGE Z1 (960 1280) – Panasonic DMC-TZ3 (960 1280) – Sony DSC-T33 (960 1280) – Sony DSC-P100 (960 1280) – Sony DSC-W5 (960 1280) – Sony DSC-T1 (960 1280) – Sony DSC-P200 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-P52 (960 1280) – Sony DSC-P10 (960 1280) – Canon PowerShot S2 IS (960 1280) – Sony DSC-H1 (960 1280) – Olympus E-510 (960 1280)

19 Sony DSC-W70 (2304 3072) – Canon PowerShot A620 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Sony DSC-W120 (2304 3072) – Sony DSC-W17 (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Pentax Optio M20 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W55 (2304 3072) – Sony DSC-W35 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Fujifilm FinePix Z10fd (2304 3072) – GEDSC A735 (2304 3072) – Sony DSC-W80 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

19 Canon IXY DIGITAL 810 IS (2448 3264) – Canon PowerShot (2448 3264) – Canon PowerShot Pro1 (2448 3264) – Canon PowerShot SD950 IS (2448 3264) – Canon PowerShot A650 IS (2448 3264) – Canon IXY DIGITAL 910 IS (2448 3264) – Canon DIGITAL IXUS 860 IS (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Canon DIGITAL IXUS 950 IS (2448 3264) – Canon PowerShot A580 (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot G9 (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Canon PowerShot S80 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Canon PowerShot SD870 IS (2448 3264)

20 Canon PowerShot SD600 (1200 1600) – Konica Minolta DiMAGE Z10 (1200 1600) – Nikon E3500 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Olympus C990Z,D490Z (1200 1600) – Sony DSC-H5 (1200 1600) – Canon PowerShot A620 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Nikon E4100 (1200 1600) – Olympus C700UZ (1200 1600) – HTC VOGU100 (1200 1600) – Nikon E2500 (1200 1600) – T-Mobile(R) Sidekick 2008 (1200 1600) – Nikon E2100 (1200 1600) – Olympus C120,D380 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot SD550 (1200 1600) – HTC TITA100 (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Fujifilm FinePix Z5fd (1200 1600)

20 Nikon COOLPIX S7c (2304 3072) – Sony DSC-W55 (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-W80 (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Olympus SP510UZ (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Olympus FE240/X795 (2304 3072) – Sony DSC-T10 (2304 3072) – Sony DSC-T20 (2448 3264) – Canon PowerShot A710 IS (2304 3072) – Nikon E7600 (2304 3072) – Olympus SP550UZ (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Olympus FE230/X790 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072)

20 Nikon E8700 (2448 3264) – Samsung NV8 , VLUU NV8 (2448 3264) – Sony DSC-T200 (2448 3264) – Sony DSC-H10 (2448 3264) – Sony DSC-T2 (2448 3264) – Vivitar ViviCam8325 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-N1 (2448 3264) – Nikon COOLPIX P50 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-W150 (2448 3264) – Fujifilm FinePix F480 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-H9 (2448 3264) – Sony DSC-T70 (2448 3264) – Sony DSC-W90 (2448 3264) – Sony DSC-T100 (2448 3264)

20 Sony DSC-F828 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-W100 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-W130 (2448 3264) – Sony DSC-T2 (2448 3264) – Sony DSC-H10 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-T200 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264) – Sony DSC-N1 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-W90 (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-W150 (2448 3264) – Sony DSC-H9 (2448 3264) – Sony DSC-T100 (2448 3264) – Sony DSC-T70 (2448 3264)

20 Sony DSC-W200 (1536 2048) – Sony DSC-P72 (1536 2048) – Konica Minolta Camera, Inc. DiMAGE Xg (1536 2048) – Konica Minolta DiMAGE Z10 (1536 2048) – Nikon E3100 (1536 2048) – Sony DSC-H3 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-W90 (1536 2048) – Nikon E3200 (1536 2048) – Sony DSC-T200 (1536 2048) – Pentax Optio W20 (1536 2048) – Sony DSC-P10 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-T100 (1536 2048) – Nikon E995 (1536 2048) – Sony DSC-H2 (1536 2048) – Sony DSC-W80 (1536 2048) – Sony DSC-H9 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-H7 (1536 2048)

21 Canon PowerShot A550 (1536 2048) – Canon PowerShot A70 (1536 2048) – Olympus X200,D560Z,C350Z (1536 2048) – Vivitar ViviCam 3705 (1536 2048) – Minolta DiMAGE Xt (1536 2048) – Sony DSC-H10 (1536 2048) – Canon PowerShot A570 IS (1536 2048) – Nikon E995 (1536 2048) – Nokia N96 (1536 2048) – Olympus C740UZ (1536 2048) – Olympus C740UZ (1536 2048) – Panasonic DMC-FZ7 (1536 2048) – Sony DSC-W50 (1536 2048) – Canon PowerShot A410 (1536 2048) – Nikon E3100 (1536 2048) – Nikon E3200 (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot SD1000 (1536 2048)

21 Canon PowerShot SD750 (1200 1600) – Canon PowerShot A650 IS (1200 1600) – Casio EX-Z75 (1200 1600) – Casio QV-R40 (1200 1600) – Pentax Optio S (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Pentax Optio S5z (1200 1600) – Canon PowerShot A410 (1200 1600) – Panasonic DMC-FZ18 (1200 1600) – Casio EX-Z60 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Casio EX-Z1000 (1200 1600) – Hewlett-Packard Photosmart R837 (1200 1600) – Canon PowerShot A430 (1200 1600) – Canon PowerShot G9 (1200 1600) – Sony DSC-H9 (1200 1600) – Casio EX-S500 (1200 1600) – Apple iPhone (1200 1600) – Casio EX-S600 (1200 1600) – Canon DIGITAL IXUS 400 (1200 1600)

21 Canon PowerShot SD750 (1536 2048) – Fujifilm FinePix J10 (1536 2048) – Casio EX-Z700 (1536 2048) – Sony DSC-H3 (1536 2048) – Sony DSC-P200 (1536 2048) – Canon PowerShot A590 IS (1536 2048) – Canon PowerShot S80 (1536 2048) – Sony DSC-P150 (1536 2048) – Canon PowerShot A620 (1536 2048) – Canon PowerShot G9 (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Sony DSC-P10 (1536 2048) – Nikon COOLPIX S8 (1536 2048) – Sony DSC-W300 (1536 2048) – Canon PowerShot TX1 (1536 2048) – Canon DIGITAL IXUS 80 IS (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot S510 (1536 2048) – Panasonic DMC-FX30 (1536 2048) – Ricoh GR DIGITAL 2 (1536 2048) – Sony DSC-H5 (1536 2048)

21 Casio EX-Z750 (2304 3072) – Sony DSC-W110 (2304 3072) – Pentax Optio M20 (2304 3072) – Olympus FE230/X790 (2304 3072) – Pentax Optio M30 (2304 3072) – Olympus SP550UZ (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-T30 (2304 3072) – Panasonic DMC-TZ3 (2304 3072) – Sony DSC-W120 (2304 3072) – Sony DSC-T50 (2304 3072) – Sony DSC-V3 (2304 3072) – Sony DSC-T10 (2304 3072) – Sony DSC-P200 (2304 3072) – Sony DSC-W7 (2304 3072) – Sony DSC-P150 (2304 3072) – Sony DSC-W70 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W55 (2304 3072)

22 Canon DIGITAL IXUS 500 (480 640) – Canon DIGITAL IXUS 50 (480 640) – Canon DIGITAL IXUS 60 (480 640) – Canon DIGITAL IXUS 950 IS (480 640) – Canon IXY DIGITAL 910 IS (480 640) – Canon PowerShot S2 IS (480 640) – Canon PowerShot SD400 (480 640) – Canon PowerShot A550 (480 640) – Canon PowerShot SD1100 IS (480 640) – Canon PowerShot SD110 (480 640) – Canon DIGITAL IXUS 70 (480 640) – Canon PowerShot S5 IS (480 640) – Canon DIGITAL IXUS 800 IS (480 640) – Canon PowerShot SD750 (480 640) – Canon PowerShot A520 (480 640) – Canon PowerShot SD1000 (480 640) – Canon PowerShot SD100 (480 640) – Canon PowerShot A560 (480 640) – Canon PowerShot SD600 (480 640) – Canon PowerShot A630 (480 640) – Canon PowerShot SD630 (480 640) – Canon PowerShot SD500 (480 640)

22 Canon IXY DIGITAL 600 (2304 3072) – Canon PowerShot SD40 (2304 3072) – Canon IXY DIGITAL 900 IS (2304 3072) – Canon PowerShot TX1 (2304 3072) – Canon PowerShot S70 (2304 3072) – Canon PowerShot A470 (2304 3072) – Canon DIGITAL IXUS 700 (2304 3072) – Canon DIGITAL IXUS 750 (2304 3072) – Canon PowerShot G6 (2304 3072) – Canon PowerShot A550 (2304 3072) – Canon PowerShot SD500 (2304 3072) – Canon DIGITAL IXUS 850 IS (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon DIGITAL IXUS 75 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot SD550 (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Canon PowerShot SD750 (2304 3072)

22 Canon PowerShot SD870 IS (2448 3264) – Nikon COOLPIX P50 (2448 3264) – Olympus E-500 (2448 3264) – Sony DSC-H9 (2448 3264) – Canon DIGITAL IXUS 80 IS (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-T100 (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-H7 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-W100 (2448 3264) – Canon PowerShot A630 (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Panasonic DMC-FZ18 (2448 3264) – Sony DSC-W90 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Canon PowerShot SX100 IS (2448 3264)

22 Konica Minolta DiMAGE A200 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Sony DSC-T2 (2448 3264) – Olympus FE280,X820,C520 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Sony DSC-N1 (2448 3264) – Nikon COOLPIX P50 (2448 3264) – Olympus SP560UZ (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-T20 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Fujifilm FinePix S8000fd (2448 3264) – Sony DSC-H3 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Canon PowerShot A630 (2448 3264) – Fujifilm FinePix Z100fd (2448 3264) – Sony DSC-T100 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-H9 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-W90 (2448 3264) – Sony DSC-T70 (2448 3264)

22 Nikon E8700 (2448 3264) – Canon PowerShot A720 IS (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-W200 (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-H7 (2448 3264) – Sony DSC-W130 (2448 3264) – Canon PowerShot SX100 IS (2448 3264) – Sony DSC-T200 (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-H9 (2448 3264) – Sony DSC-W100 (2448 3264) – Sony DSC-H10 (2448 3264) – Sony DSC-W90 (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Sony DSC-T70 (2448 3264) – Sony DSC-W150 (2448 3264) – Sony DSC-N1 (2448 3264) – Konica Minolta DiMAGE A200 (2448 3264) – Sony DSC-T100 (2448 3264)

23 Canon PowerShot A720 IS (1536 2048) – Canon PowerShot A75 (1536 2048) – Olympus C740UZ (1536 2048) – Olympus X250,D560Z,C350Z (1536 2048) – Nikon E990 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Olympus SP350 (1536 2048) – Olympus C740UZ (1536 2048) – Olympus SP550UZ (1536 2048) – Vivitar ViviCam5355 (1536 2048) – Canon PowerShot A530 (1536 2048) – Hewlett-Packard hp photosmart 720 (1536 2048) – Nikon E995 (1536 2048) – Sony Ericsson K810i (1536 2048) – Nikon E3100 (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Sony Ericsson K770i (1536 2048) – Nikon COOLPIX 5600 (1536 2048) – Sony DSC-W130 (1536 2048) – Nikon E3200 (1536 2048) – Fujifilm FinePix S304 (1536 2048) – Olympus C4100Z,C4000Z (1536 2048) – Sony Ericsson K800i (1536 2048) – Nikon E7600 (2304 3072) – Pentax Optio M20 (2304 3072) – Casio EX-Z750 (2304 3072) – Pentax Optio W20 (2304 3072) – Sanyo HD2 (2304 3072) – Sony DSC-W110 (2304 3072) – Nikon E7900 (2304 3072) – Sony DSC-W7 (2304 3072) – Samsung VLUU NV 7, NV 7 (2304 3072) – Sony DSC-T30 (2304 3072) – Sony DSC-T50 (2304 3072) – Sony DSC-P150 (2304 3072) – Sony DSC-P200 (2304 3072) – Pentax Optio M30 (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-T10 (2304 3072) – Sony DSC-W70 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-H5 (2304 3072) – Sony DSC-W120 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Sony DSC-W80 (2304 3072) – Sony DSC-W55 (2304 3072)

24 Canon DIGITAL IXUS 750 (1944 2592) – Canon DIGITAL IXUS i zoom (1944 2592) – Canon PowerShot A620 (1944 2592) – Canon PowerShot A720 IS (1944 2592) – Canon PowerShot SD550 (1944 2592) – Canon PowerShot SX100 IS (1944 2592) – Canon PowerShot A460 (1944 2592) – Canon PowerShot SD1100 IS (1944 2592) – Canon PowerShot A530 (1944 2592) – Canon PowerShot A560 (1944 2592) – Canon DIGITAL IXUS 80 IS (1944 2592) – Canon DIGITAL IXUS 75 (1944 2592) – Canon PowerShot S500 (1944 2592) – Canon PowerShot SD1000 (1944 2592) – Canon PowerShot SD870 IS (1944 2592) – Canon PowerShot SD750 (1944 2592) – Canon PowerShot SD450 (1944 2592) – Canon PowerShot SD800 IS (1944 2592) – Canon PowerShot A570 IS (1944 2592) – Canon PowerShot G10 (1944 2592) – Canon PowerShot SD850 IS (1944 2592) – Canon PowerShot A610 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Canon PowerShot SD400 (1944 2592)

24 Canon PowerShot SD40 (2304 3072) – Canon DIGITAL IXUS i7 zoom (2304 3072) – Canon DIGITAL IXUS 750 (2304 3072) – Canon IXY DIGITAL 10 (2304 3072) – Canon PowerShot SD500 (2304 3072) – Canon PowerShot G6 (2304 3072) – Canon DIGITAL IXUS 700 (2304 3072) – Canon IXY DIGITAL 900 IS (2304 3072) – Canon PowerShot A470 (2304 3072) – Canon IXY DIGITAL 700 (2304 3072) – Canon DIGITAL IXUS 850 IS (2304 3072) – Canon PowerShot S70 (2304 3072) – Canon DIGITAL IXUS 75 (2304 3072) – Canon PowerShot A550 (2304 3072) – Canon PowerShot TX1 (2304 3072) – Canon PowerShot SD550 (2304 3072) – Canon PowerShot A620 (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot SD750 (2304 3072) – Canon PowerShot SD1000 (2304 3072)

24 Canon PowerShot SD870 IS (1536 2048) – Canon DIGITAL IXUS 850 IS (1536 2048) – Canon PowerShot SD1100 IS (1536 2048) – Canon PowerShot SD200 (1536 2048) – Canon PowerShot SD550 (1536 2048) – Canon DIGITAL IXUS 75 (1536 2048) – Canon IXY DIGITAL 910 IS (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot A410 (1536 2048) – Canon PowerShot A550 (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon HV20 (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Canon PowerShot S1 IS (1536 2048) – Canon PowerShot SD450 (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Canon DIGITAL IXUS 860 IS (1536 2048) – Canon PowerShot A70 (1536 2048) – Canon PowerShot SD850 IS (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot A630 (1536 2048) – Canon DIGITAL IXUS 70 (1536 2048) – Canon PowerShot A610 (1536 2048)

26 Canon PowerShot A640 (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Casio EX-Z57 (1200 1600) – Olympus C990Z,D490Z (1200 1600) – Canon PowerShot SD450 (1200 1600) – Fujifilm FinePix E900 (1200 1600) – Sony DSC-W80 (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot G7 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Olympus u740,S740 (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Casio EX-Z9 (1200 1600) – Canon PowerShot S5 IS (1200 1600) – HTC VOGU100 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Olympus uD600,S600 (1200 1600) – Panasonic DMC-TZ3 (1200 1600) – HTC HTC.P4350 (1200 1600) – HTC TITA100 (1200 1600)

27 Panasonic DMC-LZ8 (2448 3264) – Sony DSC-W200 (2448 3264) – Canon PowerShot A590 IS (2448 3264) – Nikon COOLPIX P50 (2448 3264) – Nikon COOLPIX P5100 (2448 3264) – Canon PowerShot SD1100 IS (2448 3264) – Olympus FE340,X855,C560 (2448 3264) – Sony DSC-H10 (2448 3264) – Pentax Optio V10 (2448 3264) – Supra Super Slim XS80 (2448 3264) – Fujifilm FinePix S5800 S800 (2448 3264) – Sony DSC-T2 (2448 3264) – Canon PowerShot A630 (2448 3264) – Sony DSC-T20 (2448 3264) – Sony DSC-N1 (2448 3264) – Sony DSC-T200 (2448 3264) – Canon PowerShot SD850 IS (2448 3264) – Olympus C8080WZ (2448 3264) – Sony DSC-H7 (2448 3264) – Nikon COOLPIX S210 (2448 3264) – Canon PowerShot S5 IS (2448 3264) – Sony DSC-H9 (2448 3264) – Sony DSC-W150 (2448 3264) – Sony DSC-H3 (2448 3264) – Sony DSC-W90 (2448 3264) – Sony DSC-T100 (2448 3264) – Sony DSC-T70 (2448 3264)

27 Sony DSC-P100 (1944 2592) – Sony DSC-W1 (1944 2592) – Sony DSC-T100 (1944 2592) – V5V (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Sony DSC-P150 (1944 2592) – Sony DSC-T20 (1944 2592) – Sony DSC-W150 (1944 2592) – Sony DSC-T1 (1944 2592) – Sony DSC-W200 (1944 2592) – Canon PowerShot SX100 IS (1944 2592) – Sony DSC-H9 (1944 2592) – Sony DSC-W5 (1944 2592) – Nikon E5600 (1944 2592) – Canon PowerShot G5 (1944 2592) – Sony DSC-W70 (1944 2592) – Sony DSC-P200 (1944 2592) – Sony DSC-T33 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-T7 (1944 2592) – Canon PowerShot S60 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-W7 (1944 2592) – Sony DSC-T70 (1944 2592) – Sony DSC-F828 (1944 2592) – Sony DSC-W80 (1944 2592)

28 Canon DIGITAL IXUS 430 (1704 2272) – Canon DIGITAL IXUS 60 (1704 2272) – Canon DIGITAL IXUS 85 IS (1704 2272) – Canon PowerShot A420 (1704 2272) – Canon IXY DIGITAL 800 IS (1704 2272) – Canon PowerShot Pro1 (1704 2272) – Canon PowerShot S40 (1704 2272) – Canon PowerShot SD890 IS (1704 2272) – Canon PowerShot SD10 (1704 2272) – Canon PowerShot G7 (1704 2272) – Canon PowerShot S400 (1704 2272) – Canon DIGITAL IXUS 40 (1704 2272) – Canon PowerShot SD700 IS (1704 2272) – Canon PowerShot G3 (1704 2272) – Canon PowerShot G2 (1704 2272) – Canon PowerShot A640 (1704 2272) – Canon PowerShot A700 (1704 2272) – Canon PowerShot S410 (1704 2272) – Canon PowerShot S45 (1704 2272) – Canon PowerShot A430 (1704 2272) – Canon PowerShot SD630 (1704 2272) – Canon PowerShot A540 (1704 2272) – Canon PowerShot SD300 (1704 2272) – Canon PowerShot A85 (1704 2272) – Canon PowerShot SD600 (1704 2272) – Canon PowerShot S3 IS (1704 2272) – Canon PowerShot A80 (1704 2272) – Canon PowerShot A520 (1704 2272)

28 Canon DIGITAL IXUS 75 (1200 1600) – Canon DIGITAL IXUS v2 (1200 1600) – Canon PowerShot A40 (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot A720 IS (1200 1600) – Canon PowerShot A95 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot A520 (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot A60 (1200 1600) – Canon DIGITAL IXUS v3 (1200 1600) – Canon PowerShot S40 (1200 1600) – Canon DIGITAL IXUS 700 (1200 1600) – Canon DIGITAL IXUS 70 (1200 1600) – Canon PowerShot A85 (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Canon PowerShot A540 (1200 1600) – Canon PowerShot A410 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Canon PowerShot SD450 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot S30 (1200 1600) – Canon PowerShot S1 IS (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot A560 (1200 1600)

28 Canon PowerShot G7 (1704 2272) – Canon PowerShot S45 (1704 2272) – Canon PowerShot SD790 IS (1704 2272) – Canon DIGITAL IXUS 65 (1704 2272) – Canon PowerShot Pro1 (1704 2272) – Canon PowerShot G3 (1704 2272) – Canon IXY DIGITAL 50 (1704 2272) – Canon PowerShot A640 (1704 2272) – Canon PowerShot SD700 IS (1704 2272) – Canon DIGITAL IXUS 430 (1704 2272) – Canon DIGITAL IXUS 60 (1704 2272) – Canon PowerShot A540 (1704 2272) – Canon PowerShot SD900 (1704 2272) – Canon DIGITAL IXUS i (1704 2272) – Canon PowerShot A430 (1704 2272) – Canon PowerShot SD10 (1704 2272) – Canon DIGITAL IXUS 40 (1704 2272) – Canon PowerShot A85 (1704 2272) – Canon PowerShot G2 (1704 2272) – Canon DIGITAL IXUS 400 (1704 2272) – Canon PowerShot S410 (1704 2272) – Canon PowerShot S400 (1704 2272) – Canon PowerShot SD600 (1704 2272) – Canon PowerShot SD300 (1704 2272) – Canon PowerShot A80 (1704 2272) – Canon PowerShot SD630 (1704 2272) – Canon PowerShot A520 (1704 2272) – Canon PowerShot S3 IS (1704 2272)

29 Canon DIGITAL IXUS 40 (1200 1600) – Canon DIGITAL IXUS 50 (1200 1600) – Canon IXY DIGITAL 800 IS (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Canon PowerShot A630 (1200 1600) – Canon DIGITAL IXUS 400 (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot SD700 IS (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Canon PowerShot A550 (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Canon PowerShot SD400 (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot G7 (1200 1600) – Canon PowerShot SD630 (1200 1600) – Canon PowerShot A720 IS (1200 1600) – Canon PowerShot A580 (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Canon PowerShot A640 (1200 1600) – Canon PowerShot A560 (1200 1600) – Canon PowerShot G9 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Canon PowerShot A650 IS (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot SD450 (1200 1600)

30 Canon IXY DIGITAL 910 IS (480 640) – Canon PowerShot S500 (480 640) – Canon PowerShot SD630 (480 640) – Canon PowerShot SD300 (480 640) – Canon PowerShot SD550 (480 640) – Canon PowerShot A570 IS (480 640) – Canon PowerShot A720 IS (480 640) – Canon PowerShot S30 (480 640) – Canon PowerShot SD200 (480 640) – Canon PowerShot SD400 (480 640) – Canon PowerShot SD450 (480 640) – Canon PowerShot A630 (480 640) – Canon PowerShot SD800 IS (480 640) – Canon PowerShot SD750 (480 640) – Canon PowerShot A610 (480 640) – Canon PowerShot SD600 (480 640) – Canon PowerShot S410 (480 640) – Canon PowerShot SD750 (480 640) – Canon PowerShot G9 (480 640) – Canon DIGITAL IXUS 950 IS (480 640) – Canon PowerShot A590 IS (480 640) – Canon PowerShot SD850 IS (480 640) – Canon PowerShot S5 IS (480 640) – Canon PowerShot SD1100 IS (480 640) – Canon PowerShot A540 (480 640) – Canon PowerShot S3 IS (480 640) – Canon PowerShot SD1000 (480 640) – Canon PowerShot A520 (480 640) – Canon PowerShot A560 (480 640) – Canon PowerShot SX100 IS (480 640)

30 Olympus FE230/X790 (2304 3072) – Pentax Optio W20 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Canon DIGITAL IXUS 750 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Olympus SP510UZ (2304 3072) – Olympus SP550UZ (2304 3072) – Sony DSC-W125 (2304 3072) – Nikon E7600 (2304 3072) – Panasonic DMC-TZ3 (2304 3072) – Casio EX-Z750 (2304 3072) – Nikon E7900 (2304 3072) – Pentax Optio M30 (2304 3072) – Sony DSC-V3 (2304 3072) – Sony DSC-W7 (2304 3072) – Pentax Optio W30 (2304 3072) – Sony DSC-W110 (2304 3072) – Sony DSC-T50 (2304 3072) – Sony DSC-T30 (2304 3072) – Canon PowerShot SD750 (2304 3072) – Sony DSC-H75 (2304 3072) – Sony DSC-W120 (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Sony DSC-W70 (2304 3072) – Sony DSC-W55 (2304 3072)

32 Canon DIGITAL IXUS 40 (480 640) – Canon PowerShot A570 IS (480 640) – Canon PowerShot A75 (480 640) – Canon IXY DIGITAL 80 (480 640) – Canon DIGITAL IXUS 90 IS (480 640) – Canon PowerShot A620 (480 640) – Canon PowerShot SD10 (480 640) – Canon PowerShot S410 (480 640) – Canon PowerShot A610 (480 640) – Canon PowerShot A20 (480 640) – Canon PowerShot A40 (480 640) – Canon PowerShot G9 (480 640) – Canon PowerShot SD1100 IS (480 640) – Canon PowerShot A720 IS (480 640) – Canon PowerShot SD450 (480 640) – Canon PowerShot SD630 (480 640) – Canon DIGITAL IXUS i7 zoom (480 640) – Canon PowerShot SD400 (480 640) – Canon PowerShot S5 IS (480 640) – Canon PowerShot A95 (480 640) – Canon PowerShot A70 (480 640) – Canon PowerShot SD750 (480 640) – Canon PowerShot SD870 IS (480 640) – Canon PowerShot S200 (480 640) – Canon PowerShot A530 (480 640) – Canon PowerShot SD600 (480 640) – Canon PowerShot S2 IS (480 640) – Canon PowerShot SD1000 (480 640) – Canon PowerShot A540 (480 640) – Canon PowerShot A550 (480 640) – Canon PowerShot S3 IS (480 640) – Canon PowerShot A590 IS (480 640)



- 32 Canon DIGITAL IXUS 75 (1944 2592) – Canon PowerShot A590 IS (1944 2592) – Canon PowerShot SD1000 (1944 2592) – Canon PowerShot SD800 IS (1944 2592) – Fujifilm FinePix E510 (1944 2592) – Nikon COOLPIX S550 (1944 2592) – Nikon E5200 (1944 2592) – Canon PowerShot A610 (1944 2592) – Canon PowerShot S500 (1944 2592) – Canon PowerShot SD750 (1944 2592) – Nikon E5400 (1944 2592) – Olympus C5060WZ (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-W80 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Olympus D555Z,C315Z (1944 2592) – Sony DSC-W5 (1944 2592) – Canon PowerShot A95 (1944 2592) – Canon PowerShot S5 IS (1944 2592) – Canon PowerShot SD400 (1944 2592) – Canon PowerShot SD450 (1944 2592) – Fujifilm FinePix S5200 (1944 2592) – Nikon E5600 (1944 2592) – Canon PowerShot SD30 (1944 2592) – Nikon COOLPIX L14 (1944 2592) – Sony DSC-P100 (1944 2592) – Sony DSC-H1 (1944 2592) – Nikon COOLPIX P2 (1944 2592) – Nikon COOLPIX S210 (1944 2592) – Canon PowerShot A530 (1944 2592) – Nikon ES900 (1944 2592) – Nokia N96 (1944 2592)
- 32 Canon PowerShot SD550 (2304 3072) – HITACHI HDC756E (2304 3072) – Sony DSC-T50 (2304 3072) – Canon PowerShot A560 (2304 3072) – Canon PowerShot A710 IS (2304 3072) – Canon PowerShot SD750 (2304 3072) – Panasonic DMC-TZ3 (2304 3072) – Pentax Optio M20 (2304 3072) – Sony DSC-P200 (2304 3072) – Sanyo HD2 (2304 3072) – Sony DSC-T10 (2304 3072) – Sony DSC-W70 (2304 3072) – Canon PowerShot SD500 (2304 3072) – Pentax Optio M30 (2304 3072) – Canon PowerShot A620 (2304 3072) – Nikon COOLPIX L14 (2304 3072) – Canon PowerShot SD800 IS (2304 3072) – Polaroid Polaroid (2304 3072) – Sanyo VPC-T700 (2304 3072) – Nikon COOLPIX L12 (2304 3072) – Canon DIGITAL IXUS 70 (2304 3072) – Pentax Optio W30 (2304 3072) – Nikon COOLPIX S200 (2304 3072) – Sony DSC-W35 (2304 3072) – Sony DSC-W120 (2304 3072) – Sony DSC-H5 (2304 3072) – Nikon COOLPIX S7c (2304 3072) – Fujifilm FinePix S5700 S700 (2304 3072) – Canon PowerShot A570 IS (2304 3072) – Sony DSC-W55 (2304 3072) – Canon PowerShot SD1000 (2304 3072) – Sony DSC-W80 (2304 3072)
- 33 Canon DIGITAL IXUS 800 IS (1200 1600) – Canon IXY DIGITAL S5 (1200 1600) – Canon PowerShot SD400 (1200 1600) – Nikon COOLPIX S520 (1200 1600) – Panasonic DMC-TZ5 (1200 1600) – Sony DSC-W100 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Nikon E5600 (1200 1600) – Olympus E-510 (1200 1600) – Panasonic DMC-LZ7 (1200 1600) – Sony DSC-W90 (1200 1600) – Casio EX-S600 (1200 1600) – Panasonic DMC-TZ3 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Canon PowerShot SD750 (1200 1600) – Hewlett-Packard Photosmart M22 (V01.00) (1200 1600) – Pentax Optio S5i (1200 1600) – Apple iPhone (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Panasonic DMC-FZ50 (1200 1600) – Canon DIGITAL IXUS 55 (1200 1600) – Canon PowerShot S80 (1200 1600) – Casio EX-S500 (1200 1600) – Canon DIGITAL IXUS 970 IS (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot A95 (1200 1600) – Canon PowerShot A620 (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Nikon S1 (1200 1600) – Canon PowerShot S50 (1200 1600) – Sony DSC-T10 (1200 1600) – Casio EX-Z60 (1200 1600)
- 33 Sony DSC-T3 (1944 2592) – Pentax Optio L40 (1944 2592) – Sony DSC-T20 (1944 2592) – Sony DSC-W90 (1944 2592) – Sony DSC-N1 (1944 2592) – Sony DSC-P150 (1944 2592) – Sony DSC-H9 (1944 2592) – Sony DSC-W80 (1944 2592) – Sony DSC-H5 (1944 2592) – Sony DSC-P10 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-P92 (1944 2592) – Sony DSC-V3 (1944 2592) – Sony DSC-N2 (1944 2592) – Sony DSC-V1 (1944 2592) – Sony DSC-W120 (1944 2592) – Sony DSC-W7 (1944 2592) – Sony DSC-W100 (1944 2592) – Pentax Optio 555 (1944 2592) – Sony DSC-T70 (1944 2592) – Sony DSC-T5 (1944 2592) – Sony DSC-W70 (1944 2592) – Sony DSC-T10 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-T33 (1944 2592) – Sony DSC-P200 (1944 2592) – Nikon E5400 (1944 2592) – Sony DSC-H50 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-W15 (1944 2592) – Sony DSC-T7 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-W5 (1944 2592)
- 34 Nikon E990 (1536 2048) – Pentax Optio W20 (1536 2048) – Samsung Digimax 301 (1536 2048) – Sony DSC-H3 (1536 2048) – Sony DSC-P200 (1536 2048) – Sony DSC-T2 (1536 2048) – Sony DSC-W100 (1536 2048) – Sony DSC-W90 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-T50 (1536 2048) – Sony DSC-W120 (1536 2048) – Nikon E3200 (1536 2048) – Sony DSC-P93 (1536 2048) – Nikon E3700 (1536 2048) – Sony DSC-T20 (1536 2048) – Sony DSC-W150 (1536 2048) – Sony DSC-T100 (1536 2048) – Sony DSC-W55 (1536 2048) – Olympus C3100Z,C3020Z (1536 2048) – Konica Minolta DiMAGE Z10 (1536 2048) – Sony DSC-H5 (1536 2048) – Canon DIGITAL IXUS 70 (1536 2048) – Nikon E995 (1536 2048) – Olympus u1010,S1010 (1536 2048) – Sony DSC-P73 (1536 2048) – Sony DSC-S40 (1536 2048) – Sony DSC-H50 (1536 2048) – Sony DSC-W1 (1536 2048) – Sony DSC-T200 (1536 2048) – Sony DSC-H2 (1536 2048) – Sony DSC-W80 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-H9 (1536 2048) – Sony DSC-H7 (1536 2048)
- 36 Canon PowerShot A520 (960 1280) – Canon PowerShot SD1100 IS (960 1280) – Fujifilm FinePix S5800 S800 (960 1280) – Panasonic DMC-FS3 (960 1280) – Panasonic DMC-FX9 (960 1280) – Sony DSC-T9 (960 1280) – Canon PowerShot S3 IS (960 1280) – Nikon COOLPIX P5100 (960 1280) – Olympus C8080WZ (960 1280) – Olympus E-500 (960 1280) – Panasonic DMC-FZ18 (960 1280) – Sony DSC-H2 (960 1280) – Canon DIGITAL IXUS 75 (960 1280) – Casio QV-R62 (960 1280) – Canon PowerShot SD800 IS (960 1280) – Canon PowerShot A550 (960 1280) – Canon PowerShot A570 IS (960 1280) – Canon PowerShot SD500 (960 1280) – Canon PowerShot SD700 IS (960 1280) – Fujifilm FinePix F50SE (960 1280) – Olympus u1020,S1020 (960 1280) – Canon PowerShot G9 (960 1280) – Sony DSC-T100 (960 1280) – Canon PowerShot SD300 (960 1280) – Samsung Samsung T70 (960 1280) – Canon PowerShot SD870 IS (960 1280) – Canon PowerShot A540 (960 1280) – Olympus u770SW,S770SW (960 1280) – Apple iPhone (960 1280) – Canon PowerShot SD750 (960 1280) – Panasonic DMC-TZ1 (960 1280) – Canon PowerShot SD850 IS (960 1280) – Fujifilm FinePix S7000 (960 1280) – Canon PowerShot SD600 (960 1280) – Canon PowerShot SD1000 (960 1280) – Nikon E8700 (960 1280)
- 36 Canon PowerShot A610 (480 640) – Canon PowerShot G9 (480 640) – Canon PowerShot S5 IS (480 640) – Canon PowerShot SD1000 (480 640) – Canon PowerShot SD400 (480 640) – Olympus u790SW,S790SW (480 640) – Panasonic DMC-FX07 (480 640) – Nikon COOLPIX L18 (480 640) – Canon PowerShot A1000 IS (480 640) – Olympus uD600,S600 (480 640) – Olympus C120,D380 (480 640) – Canon PowerShot A520 (480 640) – Sony DSC-W100 (480 640) – Canon PowerShot SD1100 IS (480 640) – Fujifilm FinePix A610 (480 640) – Sony DSC-W35 (480 640) – Canon PowerShot A620 (480 640) – Canon PowerShot SD800 IS (480 640) – Supra DC 7900 (480 640) – Canon PowerShot A95 (480 640) – Nikon E8700 (480 640) – Canon PowerShot A720 IS (480 640) – JVC GZ-MG21 (480 640) – Nikon COOLPIX S210 (480 640) – Sony DSC-W55 (480 640) – Panasonic DMC-TZ3 (480 640) – Sony CYBERSHOT (480 640) – Canon PowerShot SD750 (480 640) – Sony DSC-W5 (480 640) – Nikon COOLPIX S200 (480 640) – Apple iPhone (480 640) – Sony DSC-P92 (480 640) – Sony DSC-W90 (480 640) – Olympus SP500UZ (480 640) – Panasonic DMC-TZ1 (480 640) – Sony DSC-P200 (480 640)
- 36 Olympus C3040Z (1536 2048) – Sony DSC-W100 (1536 2048) – Sony DSC-W70 (1536 2048) – Sony DSC-N2 (1536 2048) – Sony DSC-P32 (1536 2048) – Sony DSC-S90 (1536 2048) – Sony DSC-T7 (1536 2048) – Sony DSC-H10 (1536 2048) – Sony DSC-T200 (1536 2048) – Sony DSC-T9 (1536 2048) – Sony DSC-H50 (1536 2048) – Sony DSC-P52 (1536 2048) – Sony DSC-H1 (1536 2048) – Sony DSC-H5 (1536 2048) – Sony DSC-V1 (1536 2048) – Sony DSC-H7 (1536 2048) – Sony DSC-W30 (1536 2048) – Sony DSC-W30 (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-P72 (1536 2048) – Sony DSC-T50 (1536 2048) – Sony DSC-W7 (1536 2048) – Sony DSC-H2 (1536 2048) – Pentax Optio W20 (1536 2048) – Sony DSC-S40 (1536 2048) – Sony CYBERSHOT (1536 2048) – Sony DSC-L1 (1536 2048) – Sony DSC-S600 (1536 2048) – Pentax Optio 33WR (1536 2048) – Pentax Optio 30 (1536 2048) – Sony DSC-W5 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-P200 (1536 2048) – Sony DSC-P8 (1536 2048) – Sony DSC-W50 (1536 2048) – Sony DSC-H9 (1536 2048)
- 40 Sony DSC-H3 (1944 2592) – Sony DSC-H7 (1944 2592) – Sony DSC-M1 (1944 2592) – Sony DSC-T300 (1944 2592) – Sony DSC-W12 (1944 2592) – Sony DSC-W170 (1944 2592) – Sony DSC-N1 (1944 2592) – Sony DSC-P100 (1944 2592) – Sony DSC-P93A (1944 2592) – Sony DSC-T10 (1944 2592) – Sony DSC-W15 (1944 2592) – Sony DSC-H5 (1944 2592) – Sony DSC-T20 (1944 2592) – Nikon COOLPIX S550 (1944 2592) – Sony DSC-P92 (1944 2592) – Sony DSC-T5 (1944 2592) – Sony DSC-W90 (1944 2592) – Sony DSC-F828 (1944 2592) – Sony DSC-P93 (1944 2592) – Sony DSC-H9 (1944 2592) – Sony DSC-W150 (1944 2592) – Sony DSC-W120 (1944 2592) – Sony DSC-P10 (1944 2592) – Sony DSC-W200 (1944 2592) – Sony DSC-H50 (1944 2592) – Sony DSC-T100 (1944 2592) – Sony DSC-P150 (1944 2592) – Sony DSC-W7 (1944 2592) – Sony DSC-T33 (1944 2592) – Sony DSC-T1 (1944 2592) – Sony DSC-W1 (1944 2592) – Sony DSC-W70 (1944 2592) – Sony DSC-W5 (1944 2592) – Sony DSC-T7 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-T70 (1944 2592) – Sony DSC-W80 (1944 2592) – Sony DSC-P200 (1944 2592)
- 44 Canon PowerShot A550 (1944 2592) – Nikon E5400 (1944 2592) – Sony DSC-W35 (1944 2592) – Sony DSC-T300 (1944 2592) – Sony DSC-T77 (1944 2592) – Sony DSC-W300 (1944 2592) – Canon PowerShot A610 (1944 2592) – Nikon E7900 (1944 2592) – Sony DSC-W170 (1944 2592) – Sony DSC-T200 (1944 2592) – Sony DSC-T100 (1944 2592) – Sony DSC-H3 (1944 2592) – Sony DSC-T30 (1944 2592) – Sony DSC-W90 (1944 2592) – Sony DSC-W100 (1944 2592) – Sony DSC-T20 (1944 2592) – Sony DSC-T10 (1944 2592) – Sony DSC-V1 (1944 2592) – Sony DSC-H9 (1944 2592) – Sony DSC-N1 (1944 2592) – Sony DSC-T5 (1944 2592) – Sony DSC-N2 (1944 2592) – Sony DSC-P92 (1944 2592) – Sony DSC-W7 (1944 2592) – Sony DSC-W80 (1944 2592) – Sony DSC-W15 (1944 2592) – Sony DSC-W200 (1944 2592) – Sony DSC-H50 (1944 2592) – Sony DSC-H5 (1944 2592) – Sony DSC-P10 (1944 2592) – Sony DSC-T2 (1944 2592) – Sony DSC-W120 (1944 2592) – Sony DSC-P150 (1944 2592) – Sony DSC-T33 (1944 2592) – Canon IXY DIGITAL 2000 IS (1944 2592) – Sony DSC-W70 (1944 2592) – Sony DSC-H1 (1944 2592) – Sony DSC-W5 (1944 2592) – Nikon COOLPIX L3 (1944 2592) – Sony DSC-T70 (1944 2592) – Sony DSC-W55 (1944 2592) – Sony DSC-T7 (1944 2592) – Sony DSC-P200 (1944 2592) – Sony DSC-W150 (1944 2592)
- 45 Sony DSC-P120 (1536 2048) – Sony DSC-S90 (1536 2048) – Sony DSC-T5 (1536 2048) – Sony DSC-W7 (1536 2048) – Sony DSC-T10 (1536 2048) – Sony DSC-W100 (1536 2048) – Sony DSC-W200 (1536 2048) – Sony DSC-W50 (1536 2048) – Sony DSC-W5 (1536 2048) – Sony DSC-P72 (1536 2048) – Sony DSC-P8 (1536 2048) – Sony DSC-T300 (1536 2048) – Sony DSC-T7 (1536 2048) – Sony DSC-W90 (1536 2048) – Sony DSC-S600 (1536 2048) – Sony DSC-W150 (1536 2048) – Sony DSC-W30 (1536 2048) – Nikon E995 (1536 2048) – Sony DSC-P10 (1536 2048) – Sony DSC-H3 (1536 2048) – Sony DSC-W120 (1536 2048) – Sony DSC-L1 (1536 2048) – Sony DSC-T1 (1536 2048) – Nikon E3700 (1536 2048) – Sony DSC-P200 (1536 2048) – Sony DSC-T70 (1536 2048) – Sony DSC-T9 (1536 2048) – Sony DSC-H5 (1536 2048) – Sony DSC-S40 (1536 2048) – Sony DSC-T100 (1536 2048) – Sony DSC-H2 (1536 2048) – Konica Minolta DiMAGE Z10 (1536 2048) – Sony DSC-H50 (1536 2048) – Sony DSC-P73 (1536 2048) – Sony DSC-T200 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-T20 (1536 2048) – Pentax Optio W20 (1536 2048) – Sony CYBERSHOT (1536 2048) – Sony DSC-P93 (1536 2048) – Sony DSC-H7 (1536 2048) – Sony DSC-H9 (1536 2048) – Sony DSC-W1 (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-W80 (1536 2048)
- 46 Canon PowerShot S80 (1944 2592) – Canon PowerShot SD500 (1944 2592) – Canon DIGITAL IXUS i5 (1944 2592) – Canon DIGITAL IXUS 82 IS (1944 2592) – Canon PowerShot SD950 IS (1944 2592) – Canon DIGITAL IXUS 70 (1944 2592) – Canon DIGITAL IXUS i zoom (1944 2592) – Canon PowerShot A590 IS (1944 2592) – Canon DIGITAL IXUS 80 IS (1944 2592) – Canon PowerShot A710 IS (1944 2592) – Canon PowerShot G5 (1944 2592) – Canon PowerShot SD550 (1944 2592) – Canon PowerShot S60 (1944 2592) – Canon DIGITAL IXUS 500 (1944 2592) – Canon PowerShot A630 (1944 2592) – Canon PowerShot SD30 (1944 2592) – Canon DIGITAL IXUS 860 IS (1944 2592) – Canon PowerShot A620 (1944 2592) – Canon PowerShot A550 (1944 2592) – Canon PowerShot SD20 (1944 2592) – Canon PowerShot A560 (1944 2592) – Canon DIGITAL IXUS 75 (1944 2592) – Canon PowerShot A720 IS (1944 2592) – Canon DIGITAL IXUS 55 (1944 2592) – Canon PowerShot S500 (1944 2592) – Canon PowerShot S50 (1944 2592) – Canon PowerShot SD430 WIRELESS (1944 2592) – Canon PowerShot SX100 IS (1944 2592) – Canon PowerShot SD870 IS (1944 2592) – Canon PowerShot A570 IS (1944 2592) – Canon PowerShot A650 IS (1944 2592) – Canon DIGITAL IXUS 50 (1944 2592) – Canon PowerShot G9 (1944 2592) – Canon PowerShot SD850 IS (1944 2592) – Canon PowerShot A460 (1944 2592) – Canon PowerShot SD1100 IS (1944 2592) – Canon PowerShot S5 IS (1944 2592) – Canon PowerShot SD800 IS (1944 2592) – Canon PowerShot SD1000 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Canon PowerShot SD400 (1944 2592) – Canon PowerShot SD450 (1944 2592) – Canon PowerShot A610 (1944 2592) – Canon PowerShot A95 (1944 2592) – Canon PowerShot SD750 (1944 2592) – Canon PowerShot A530 (1944 2592)

46 Canon PowerShot TX1 (1944 2592) – Canon PowerShot SD30 (1944 2592) – Canon DIGITAL IXUS 950 IS (1944 2592) – Canon DIGITAL IXUS 75 (1944 2592) – Canon IXY DIGITAL 60 (1944 2592) – Canon PowerShot A630 (1944 2592) – Canon DIGITAL IXUS 860 IS (1944 2592) – Canon PowerShot A470 (1944 2592) – Canon DIGITAL IXUS i zoom (1944 2592) – Canon PowerShot A620 (1944 2592) – Canon DIGITAL IXUS 500 (1944 2592) – Canon PowerShot A710 IS (1944 2592) – Canon PowerShot A550 (1944 2592) – Canon PowerShot G6 (1944 2592) – Canon PowerShot A570 IS (1944 2592) – Canon PowerShot A650 IS (1944 2592) – Canon PowerShot SD550 (1944 2592) – Canon PowerShot SD1100 IS (1944 2592) – Canon PowerShot A560 (1944 2592) – Canon PowerShot A590 IS (1944 2592) – Canon DIGITAL IXUS 850 IS (1944 2592) – Canon PowerShot SX100 IS (1944 2592) – Canon PowerShot S80 (1944 2592) – Canon PowerShot SD800 IS (1944 2592) – Canon PowerShot SD950 IS (1944 2592) – Canon PowerShot A95 (1944 2592) – Canon PowerShot S50 (1944 2592) – Canon DIGITAL IXUS 80 IS (1944 2592) – Canon IXY DIGITAL 55 (1944 2592) – Canon DIGITAL IXUS 55 (1944 2592) – Canon PowerShot G5 (1944 2592) – Canon PowerShot SD850 IS (1944 2592) – Canon DIGITAL IXUS 50 (1944 2592) – Canon PowerShot S500 (1944 2592) – Canon PowerShot SD750 (1944 2592) – Canon PowerShot S5 IS (1944 2592) – Canon PowerShot A720 IS (1944 2592) – Canon PowerShot S60 (1944 2592) – Canon PowerShot SD1000 (1944 2592) – Canon PowerShot G9 (1944 2592) – Canon PowerShot SD870 IS (1944 2592) – Canon PowerShot SD400 (1944 2592) – Canon PowerShot S2 IS (1944 2592) – Canon PowerShot A610 (1944 2592) – Canon PowerShot SD450 (1944 2592) – Canon PowerShot A530 (1944 2592) – Canon DIGITAL IXUS 860 IS (1536 2048) – Canon PowerShot A310 (1536 2048) – Canon PowerShot SD100 (1536 2048) – Canon DIGITAL IXUS 850 IS (1536 2048) – Canon PowerShot G6 (1536 2048) – Canon VIXIA HF100 (1536 2048) – Canon PowerShot SD110 (1536 2048) – Canon HV10 (1536 2048) – Canon PowerShot A550 (1536 2048) – Canon DIGITAL IXUS 70 (1536 2048) – Canon PowerShot A470 (1536 2048) – Canon PowerShot A630 (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Canon PowerShot SD20 (1536 2048) – Canon DIGITAL IXUS 80 IS (1536 2048) – Canon PowerShot A590 IS (1536 2048) – Canon PowerShot SD850 IS (1536 2048) – Canon DIGITAL IXUS 75 (1536 2048) – Canon PowerShot A460 (1536 2048) – Canon PowerShot A530 (1536 2048) – Canon PowerShot S500 (1536 2048) – Canon PowerShot S1 IS (1536 2048) – Canon DIGITAL IXUS 50 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Canon PowerShot A610 (1536 2048) – Canon PowerShot S30 (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon PowerShot A410 (1536 2048) – Canon PowerShot SD550 (1536 2048) – Canon PowerShot SD870 IS (1536 2048) – Canon PowerShot SD450 (1536 2048) – Canon PowerShot SD1100 IS (1536 2048) – Canon PowerShot A400 (1536 2048) – Canon PowerShot A70 (1536 2048) – Canon PowerShot S230 (1536 2048) – Canon PowerShot A720 IS (1536 2048) – Canon PowerShot A710 IS (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Canon PowerShot SD200 (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot A620 (1536 2048) – Canon PowerShot A75 (1536 2048) – Canon PowerShot A95 (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Canon PowerShot SD750 (1536 2048) – Canon PowerShot A570 IS (1536 2048) – Canon PowerShot A510 (1536 2048)

48

49 Konica Minolta Camera, Inc. DiMAGE Xg (1536 2048) – Minolta DiMAGE Z1 (1536 2048) – Sony DSC-T7 (1536 2048) – Sony DSC-W150 (1536 2048) – Sony DSC-W35 (1536 2048) – Pentax Optio 30 (1536 2048) – Sony DSC-T33 (1536 2048) – Sony DSC-W200 (1536 2048) – Sony DSC-W70 (1536 2048) – Sony DSC-W90 (1536 2048) – Sony MVC-CD350 (1536 2048) – Sony DSC-W7 (1536 2048) – Sony DSC-P32 (1536 2048) – Sony DSC-T200 (1536 2048) – Sony DSC-W110 (1536 2048) – Sony DSC-W30 (1536 2048) – Sony DSC-W5 (1536 2048) – Sony DSC-S90 (1536 2048) – Sony DSC-T10 (1536 2048) – Sony DSC-H3 (1536 2048) – Sony DSC-T100 (1536 2048) – Sony DSC-W100 (1536 2048) – Sony DSC-W80 (1536 2048) – Sony DSC-P10 (1536 2048) – Sony DSC-P72 (1536 2048) – Sony CD MAVICA (1536 2048) – Nikon E885 (1536 2048) – Sony DSC-P8 (1536 2048) – Sony DSC-L1 (1536 2048) – Sony DSC-P52 (1536 2048) – Sony DSC-H7 (1536 2048) – Konica Minolta DiMAGE Z10 (1536 2048) – Sony DSC-T9 (1536 2048) – Sony DSC-H1 (1536 2048) – Sony DSC-T50 (1536 2048) – Sony DSC-S600 (1536 2048) – Sony DSC-W50 (1536 2048) – Sony DSC-W120 (1536 2048) – Sony DSC-H50 (1536 2048) – Sony DSC-H5 (1536 2048) – Sony DSC-T70 (1536 2048) – Sony DSC-H2 (1536 2048) – Sony DSC-T20 (1536 2048) – Sony DSC-W55 (1536 2048) – Sony DSC-P200 (1536 2048) – Pentax Optio W20 (1536 2048) – Sony DSC-S40 (1536 2048) – Sony DSC-H9 (1536 2048) – Sony CYBERSHOT (1536 2048) – Canon PowerShot A300 (1536 2048) – Canon PowerShot S70 (1536 2048) – Canon PowerShot S80 (1536 2048) – Canon PowerShot SD550 (1536 2048) – Canon VIXIA HF100 (1536 2048) – Canon DIGITAL IXUS 30 (1536 2048) – Canon IXY DIGITAL L2 (1536 2048) – Canon IXY DIGITAL L3 (1536 2048) – Canon PowerShot S60 (1536 2048) – Canon DIGITAL IXUS 80 IS (1536 2048) – Canon DIGITAL IXUS 860 IS (1536 2048) – Canon PowerShot SD110 (1536 2048) – Canon DIGITAL IXUS 70 (1536 2048) – Canon DIGITAL IXUS 75 (1536 2048) – Canon PowerShot SD100 (1536 2048) – Canon PowerShot SD500 (1536 2048) – Canon PowerShot A530 (1536 2048) – Canon DIGITAL IXUS v3 (1536 2048) – Canon PowerShot A550 (1536 2048) – Canon IXY DIGITAL 910 IS (1536 2048) – Canon PowerShot A410 (1536 2048) – Canon IXY DIGITAL 90 (1536 2048) – Canon PowerShot SD1100 IS (1536 2048) – Canon DIGITAL IXUS 950 IS (1536 2048) – Canon PowerShot A590 IS (1536 2048) – Canon PowerShot A400 (1536 2048) – Canon PowerShot A720 IS (1536 2048) – Canon HV20 (1536 2048) – Canon PowerShot S1 IS (1536 2048) – Canon IXY DIGITAL 900 IS (1536 2048) – Canon PowerShot A630 (1536 2048) – Canon DIGITAL IXUS 50 (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot A70 (1536 2048) – Canon PowerShot A75 (1536 2048) – Canon PowerShot S30 (1536 2048) – Canon PowerShot S500 (1536 2048) – Canon PowerShot SD850 IS (1536 2048) – Canon PowerShot A610 (1536 2048) – Canon PowerShot SD450 (1536 2048) – Canon PowerShot SD200 (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Canon PowerShot A570 IS (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon PowerShot A620 (1536 2048) – Canon PowerShot SD870 IS (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Canon PowerShot S230 (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Canon PowerShot SD750 (1536 2048) – Canon PowerShot SD1000 (1536 2048)

61 Canon PowerShot S3 IS (1536 2048) – Casio EX-S10 (1536 2048) – Olympus u740,5740 (1536 2048) – Panasonic DMC-FZ7 (1536 2048) – Panasonic DMC-TZ3 (1536 2048) – Canon PowerShot A610 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Casio EX-P600 (1536 2048) – Fujifilm FinePix S5100 (1536 2048) – Olympus E-500 (1536 2048) – Panasonic DMC-FX500 (1536 2048) – Canon DIGITAL IXUS 75 (1536 2048) – Casio EX-S880 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Panasonic DMC-TZ2 (1536 2048) – Sony DSC-P92 (1536 2048) – Sony DSC-S600 (1536 2048) – Sony DSC-W100 (1536 2048) – Canon PowerShot A650 IS (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot SD870 IS (1536 2048) – Panasonic DMC-TZ5 (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Sony DSC-W80 (1536 2048) – Canon PowerShot A710 IS (1536 2048) – Casio EX-Z110 (1536 2048) – Sony DSC-T1 (1536 2048) – Sony Ericsson K810i (1536 2048) – Fujifilm FinePix S5700 S700 (1536 2048) – Canon PowerShot A640 (1536 2048) – Canon PowerShot SD600 (1536 2048) – Nikon COOLPIX S610 (1536 2048) – Olympus E-520 (1536 2048) – Nikon E995 (1536 2048) – Sony CYBERSHOT (1536 2048) – Canon PowerShot SD770 IS (1536 2048) – Nikon COOLPIX S200 (1536 2048) – Canon IXY DIGITAL 70 (1536 2048) – Canon PowerShot A620 (1536 2048) – Canon PowerShot G9 (1536 2048) – Olympus E-300 (1536 2048) – Fujifilm FinePix J50 (1536 2048) – Casio EX-Z600 (1536 2048) – Fujifilm FinePix S9600 (1536 2048) – Olympus u10D,S300D,u300D (1536 2048) – Panasonic DMC-TZ15 (1536 2048) – Canon PowerShot A570 IS (1536 2048) – Sony DSC-W55 (1536 2048) – Nikon COOLPIX P5000 (1536 2048) – Canon DIGITAL IXUS 90 IS (1536 2048) – Sony Ericsson K800i (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Canon PowerShot SD950 IS (1536 2048) – Panasonic DMC-FZ18 (1536 2048) – Casio EX-Z75 (1536 2048) – Canon DIGITAL IXUS 800 IS (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot A720 IS (1536 2048) – Canon PowerShot SD750 (1536 2048) – Sony DSC-W70 (1536 2048) – Casio EX-Z850 (1536 2048)

64 Apple iPhone (1200 1600) – Canon DIGITAL IXUS 75 (1200 1600) – Canon PowerShot SD700 IS (1200 1600) – Fujifilm FinePix Z10fd (1200 1600) – Olympus E-420 (1200 1600) – Panasonic DMC-FZ8 (1200 1600) – Sony DSC-S700 (1200 1600) – Canon PowerShot SD30 (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Canon PowerShot SP560UZ (1200 1600) – Samsung <KENOX S1050 / Samsung S1050> (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Fujifilm FinePix F40fd (1200 1600) – Fujifilm FinePix F50SE (1200 1600) – LG Electronics Inc LG-VX8560 (1200 1600) – Panasonic DMC-FZ30 (1200 1600) – Canon PowerShot A550 (1200 1600) – Fujifilm FinePix Z1 (1200 1600) – Sony DSC-H10 (1200 1600) – Canon PowerShot G5 (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Fujifilm FinePix F31fd (1200 1600) – Canon PowerShot G10 (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Fujifilm FinePix E500 (1200 1600) – Fujifilm FinePix S5200 (1200 1600) – Sony DSC-T20 (1200 1600) – Canon DIGITAL IXUS 500 (1200 1600) – Canon DIGITAL IXUS 750 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Fujifilm FinePix S9500 (1200 1600) – Nikon E5900 (1200 1600) – Sony DSC-S730 (1200 1600) – Panasonic DMC-FX7 (1200 1600) – Panasonic DMC-FZ18 (1200 1600) – Canon PowerShot A640 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Samsung < Digimax U-CA 5, Kenox U-CA 5 / Kenox U-CA 50 > (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Olympus u1030SW,S1030SW (1200 1600) – Sony DSC-T100 (1200 1600) – Olympus E-410 (1200 1600) – Sony DSC-H50 (1200 1600) – Fujifilm FinePix Z2 (1200 1600) – Panasonic DMC-FZ5 (1200 1600) – Sony DSC-W90 (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Fujifilm FinePix F20 (1200 1600) – Sony DSC-W55 (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Panasonic DMC-TZ3 (1200 1600) – Canon PowerShot A720 IS (1200 1600) – Canon PowerShot G9 (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Sony DSC-F828 (1200 1600) – Pentax Optio A30 (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Samsung L73 (1200 1600) – Canon DIGITAL IXUS 700 (1200 1600) – Olympus E-510 (1200 1600) – Fujifilm FinePix S5700 S700 (1200 1600)

65 Canon DIGITAL IXUS 70 (2100 2800) – Canon PowerShot A590 IS (2100 2800) – Fujifilm FinePix F30 (2100 2800) – Fujifilm FinePix S6500fd (2100 2800) – Nikon COOLPIX P80 (2100 2800) – Nikon COOLPIX S210 (2100 2800) – Nikon COOLPIX S50 (2100 2800) – Olympus C8080WZ (2100 2800) – Olympus E-410 (2100 2800) – Olympus E-500 (2100 2800) – Canon PowerShot G7 (2100 2800) – Canon PowerShot SD790 IS (2100 2800) – Fujifilm FinePix E550 (2100 2800) – Fujifilm FinePix S5800 S800 (2100 2800) – Panasonic DMC-FX01 (2100 2800) – Panasonic DMC-TZ3 (2100 2800) – Pentax Optio W10 (2100 2800) – Sony DSC-H50 (2100 2800) – Canon DIGITAL IXUS 85 IS (2100 2800) – Fujifilm FinePix F47fd (2100 2800) – Fujifilm FinePix S6000fd (2100 2800) – Olympus E-510 (2100 2800) – Olympus FE280,X820,C520 (2100 2800) – Olympus u720SW,S720SW (2100 2800) – Panasonic DMC-LZ7 (2100 2800) – Ricoh Caplio GX100 (2100 2800) – Samsung <VLUU L830 / Samsung L830> (2100 2800) – Sanyo EI (2100 2800) – Sony DSC-H9 (2100 2800) – Canon PowerShot SD800 IS (2100 2800) – Nikon COOLPIX L11 (2100 2800) – Olympus u740,5740 (2100 2800) – Pentax Optio A20 (2100 2800) – Sony DSC-W50 (2100 2800) – Fujifilm FinePix S1000fd (2100 2800) – Canon DIGITAL IXUS 80 IS (2100 2800) – Canon PowerShot A540 (2100 2800) – Canon PowerShot SD870 IS (2100 2800) – Panasonic DMC-FX07 (2100 2800) – Canon PowerShot A640 (2100 2800) – Panasonic DMC-FZ8 (2100 2800) – Sony DSC-H7 (2100 2800) – Canon PowerShot SD700 IS (2100 2800) – Canon PowerShot SD1100 IS (2100 2800) – Samsung <KENOX S630 / Samsung S630> (2100 2800) – Canon PowerShot G9 (2100 2800) – Olympus SP500UZ (2100 2800) – Ricoh GR DIGITAL 2 (2100 2800) – Canon PowerShot A720 IS (2100 2800) – Nikon COOLPIX S200 (2100 2800) – Sony DSC-W200 (2100 2800) – Canon PowerShot SD750 (2100 2800) – Panasonic DMC-FZ18 (2100 2800) – Sony DSC-S650 (2100 2800) – Sony DSC-W80 (2100 2800) – Canon PowerShot SD1000 (2100 2800) – Canon PowerShot A710 IS (2100 2800) – Nikon COOLPIX S10 (2100 2800) – Fujifilm FinePix S5700 S700 (2100 2800) – Canon PowerShot SX100 IS (2100 2800) – Canon PowerShot SD600 (2100 2800) – Canon PowerShot S5 IS (2100 2800) – Olympus SP510UZ (2100 2800) – Canon PowerShot SD850 IS (2100 2800) – Canon PowerShot S3 IS (2100 2800)

72 Canon PowerShot A720 IS (1200 1600) – Canon PowerShot SD630 (1200 1600) – Canon PowerShot S500 (1200 1600) – Canon PowerShot SD110 (1200 1600) – Canon DIGITAL IXUS 430 (1200 1600) – Canon PowerShot A20 (1200 1600) – Canon PowerShot A75 (1200 1600) – Canon PowerShot S400 (1200 1600) – Canon PowerShot SD400 (1200 1600) – Canon PowerShot S410 (1200 1600) – Canon DIGITAL IXUS 40 (1200 1600) – Canon PowerShot A700 (1200 1600) – Canon PowerShot A80 (1200 1600) – Canon PowerShot G6 (1200 1600) – Canon PowerShot SD200 (1200 1600) – Canon DIGITAL IXUS 55 (1200 1600) – Canon PowerShot SD900 (1200 1600) – Canon PowerShot A590 IS (1200 1600) – Canon PowerShot A640 (1200 1600) – Canon PowerShot G7 (1200 1600) – Canon PowerShot SD770 IS (1200 1600) – Canon PowerShot A550 (1200 1600) – Canon PowerShot A620 (1200 1600) – Canon PowerShot SD500 (1200 1600) – Canon DIGITAL IXUS 60 (1200 1600) – Canon IXY DIGITAL 900 IS (1200 1600) – Canon PowerShot S330 (1200 1600) – Canon DIGITAL IXUS v2 (1200 1600) – Canon PowerShot SD950 IS (1200 1600) – Canon PowerShot A630 (1200 1600) – Canon PowerShot SD300 (1200 1600) – Canon DIGITAL IXUS 860 IS (1200 1600) – Canon PowerShot S80 (1200 1600) – Canon PowerShot G3 (1200 1600) – Canon DIGITAL IXUS 800 IS (1200 1600) – Canon PowerShot G2 (1200 1600) – Canon DIGITAL IXUS 950 IS (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Canon PowerShot A470 (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Canon PowerShot G10 (1200 1600) – Canon PowerShot S110 (1200 1600) – Canon PowerShot S50 (1200 1600) – Canon PowerShot A520 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Canon PowerShot A200 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot A60 (1200 1600) – Canon PowerShot A540 (1200 1600) – Canon PowerShot S200 (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Canon PowerShot A650 IS (1200 1600) – Canon PowerShot S30 (1200 1600) – Canon PowerShot A560 (1200 1600) – Canon PowerShot SD550 (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Canon PowerShot A510 (1200 1600) – Canon DIGITAL IXUS 70 (1200 1600) – Canon DIGITAL IXUS II (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot SD700 IS (1200 1600) – Canon PowerShot A40 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon DIGITAL IXUS 50 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot G9 (1200 1600) – Canon PowerShot S3 IS (1200 1600)

80 Canon DIGITAL IXUS v2 (1200 1600) – Canon DIGITAL IXUS v3 (1200 1600) – Canon IXY DIGITAL 70 (1200 1600) – Canon PowerShot A400 (1200 1600) – Canon PowerShot A75 (1200 1600) – Canon PowerShot SD500 (1200 1600) – Canon PowerShot SD950 IS (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Canon PowerShot SD790 IS (1200 1600) – Canon PowerShot A700 (1200 1600) – Canon PowerShot G7 (1200 1600) – Canon PowerShot SD30 (1200 1600) – Canon PowerShot SD790 IS (1200 1600) – Canon DIGITAL IXUS 800 IS (1200 1600) – Canon PowerShot S40 (1200 1600) – Canon DIGITAL IXUS 60 (1200 1600) – Canon DIGITAL IXUS 65 (1200 1600) – Canon PowerShot A550 (1200 1600) – Canon PowerShot S110 (1200 1600) – Canon DIGITAL IXUS 860 IS (1200 1600) – Canon PowerShot A580 (1200 1600) – Canon PowerShot A70 (1200 1600) – Canon PowerShot S410 (1200 1600) – Canon PowerShot S50 (1200 1600) – Canon DIGITAL IXUS 70 (1200 1600) – Canon PowerShot A460 (1200 1600) – Canon PowerShot S45 (1200 1600) – Canon PowerShot S200 (1200 1600) – Canon DIGITAL IXUS 950 IS (1200 1600) – Canon PowerShot A470 (1200 1600) – Canon PowerShot S400 (1200 1600) – Canon PowerShot SX100 IS (1200 1600) – Canon PowerShot S330 (1200 1600) – Canon PowerShot A40 (1200 1600) – Canon PowerShot S300 (1200 1600) – Canon DIGITAL IXUS 700 (1200 1600) – Canon DIGITAL IXUS 30 (1200 1600) – Canon PowerShot A410 (1200 1600) – Canon DIGITAL IXUS 500 (1200 1600) – Canon DIGITAL IXUS 55 (1200 1600) – Canon PowerShot A430 (1200 1600) – Canon PowerShot A620 (1200 1600) – Canon PowerShot SD900 (1200 1600) – Canon PowerShot A640 (1200 1600) – Canon PowerShot SD200 (1200 1600) – Canon PowerShot SD700 IS (1200 1600) – Canon PowerShot A630 (1200 1600) – Canon PowerShot A590 IS (1200 1600) – Canon PowerShot G2 (1200 1600) – Canon PowerShot A510 (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Canon DIGITAL IXUS 75 (1200 1600) – Canon PowerShot A95 (1200 1600) – Canon PowerShot A530 (1200 1600) – Canon PowerShot SD300 (1200 1600) – Canon PowerShot SD450 (1200 1600) – Canon PowerShot A60 (1200 1600) – Canon PowerShot A540 (1200 1600) – Canon PowerShot A420 IS (1200 1600) – Canon PowerShot SD550 (1200 1600) – Canon PowerShot SD630 (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot S1 IS (1200 1600) – Canon PowerShot A560 (1200 1600) – Canon PowerShot A520 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Canon PowerShot SD400 (1200 1600) – Canon PowerShot A80 (1200 1600) – Canon PowerShot G10 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Canon PowerShot SD600 (1200 1600) – Canon PowerShot S30 (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Canon PowerShot SD750 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Canon PowerShot G9 (1200 1600)

87 Canon PowerShot A540 (960 1280) – Canon PowerShot A560 (960 1280) – Canon PowerShot A620 (960 1280) – Canon PowerShot A630 (960 1280) – Canon PowerShot G10 (960 1280) – Canon PowerShot SD630 (960 1280) – Panasonic DMC-FS3 (960 1280) – Panasonic DMC-FS5 (960 1280) – Panasonic DMC-LZ5 (960 1280) – Panasonic DMC-TZ5 (960 1280) – Sony DSC-T10 (960 1280) – Canon DIGITAL IXUS 75 (960 1280) – Canon PowerShot G6 (960 1280) – Fujifilm FinePix F31fd (960 1280) – Fujifilm FinePix S8000fd (960 1280) – Nikon COOLPIX L6 (960 1280) – Panasonic DMC-FX30 (960 1280) – Sony DSC-T200 (960 1280) – Canon PowerShot A430 (960 1280) – Canon PowerShot A530 (960 1280) – Canon PowerShot G7 (960 1280) – Hewlett-Packard Photosmart R840 (960 1280) – Olympus u1050SW,S1050SW (960 1280) – Panasonic DMC-FX01 (960 1280) – Pentax Optio M30 (960 1280) – Samsung L73 (960 1280) – Casio EX-S10 (960 1280) – Sony DSC-T100 (960 1280) – Sony DSC-W55 (960 1280) – Canon DIGITAL IXUS 40 (960 1280) – Canon PowerShot A610 (960 1280) – Casio EX-Z57 (960 1280) – Nikon COOLPIX S51 (960 1280) – Sony DSC-W50 (960 1280) – Sony DSC-W90 (960 1280) – Canon PowerShot A720 IS (960 1280) – Fujifilm FinePix F10 (960 1280) – Olympus u1030SW,S1030SW (960 1280) – Panasonic DMC-FX55 (960 1280) – Panasonic DMC-FZ18 (960 1280) – Panasonic DMC-TZ1 (960 1280) – Canon PowerShot S2 IS (960 1280) – Olympus FE190/X750 (960 1280) – Sony DSC-P120 (960 1280) – Sony DSC-W80 (960 1280) – Canon DIGITAL IXUS 90 IS (960 1280) – Nikon E3200 (960 1280) – Canon HV20 (960 1280) – Fujifilm FinePix Z5fd (960 1280) – Canon PowerShot S80 (960 1280) – Panasonic DMC-LX3 (960 1280) – Samsung VLUU L100, M100 / Samsung L100, M100 (960 1280) – Sony Ericsson K810i (960 1280) – Canon DIGITAL IXUS 500 (960 1280) – Canon PowerShot SD850 IS (960 1280) – Canon DIGITAL IXUS 950 IS (960 1280) – Panasonic DMC-TZ3 (960 1280) – Canon PowerShot S3 IS (960 1280) – Olympus u720SW,S720SW (960 1280) – Casio EX-S880 (960 1280) – Canon PowerShot SD870 IS (960 1280) – Panasonic DMC-FZ50 (960 1280) – Olympus FE280,X820,C520 (960 1280) – Canon PowerShot SD950 IS (960 1280) – Sony DSC-H5 (960 1280) – Canon PowerShot SD600 (960 1280) – Sony DSC-H9 (960 1280) – Canon DIGITAL IXUS 850 IS (960 1280) – Canon DIGITAL IXUS 70 (960 1280) – Canon PowerShot SD500 (960 1280) – Fujifilm FinePix S9600 (960 1280) – Sony DSC-V1 (960 1280) – Apple iPhone (960 1280) – Canon PowerShot SD1000 (960 1280) – Canon IXY DIGITAL 800 IS (960 1280) – Panasonic DMC-FX12 (960 1280) – Canon PowerShot SD800 IS (960 1280) – Canon PowerShot S5 IS (960 1280) – Casio EX-Z1050 (960 1280) – Panasonic DMC-LZ7 (960 1280) – Canon PowerShot G9 (960 1280) – Canon PowerShot SD1100 IS (960 1280) – Olympus E-500 (960 1280) – Canon PowerShot SD750 (960 1280) – Canon PowerShot SD400 (960 1280) – Fujifilm FinePix S100FS (960 1280) – Canon DIGITAL IXUS 860 IS (960 1280)

89 Canon PowerShot A540 (1200 1600) – Canon PowerShot SD450 (1200 1600) – Casio EX-Z750 (1200 1600) – Nikon COOLPIX S4 (1200 1600) – Nikon E5400 (1200 1600) – Olympus u850SW,S850SW (1200 1600) – Sony DSC-T7 (1200 1600) – Sony DSC-W120 (1200 1600) – Sony Ericsson K800i (1200 1600) – Canon DIGITAL IXUS 860 IS (1200 1600) – Canon PowerShot A560 (1200 1600) – Canon PowerShot SD900 (1200 1600) – Fujifilm FinePix S7000 (1200 1600) – Fujifilm FinePix S9100 (1200 1600) – Nikon E5600 (1200 1600) – Olympus SP550UZ (1200 1600) – Panasonic DMC-FX33 (1200 1600) – Pentax Optio A10 (1200 1600) – Samsung <Samsung L74, Samsung VLUU L74> (1200 1600) – Samsung <Samsung NV3, Samsung VLUU NV3> (1200 1600) – Fujifilm FinePix A820 (1200 1600) – Fujifilm FinePix S9600 (1200 1600) – Nikon COOLPIX L11 (1200 1600) – Panasonic DMC-TZ3 (1200 1600) – Sony DSC-M1 (1200 1600) – Canon PowerShot A620 (1200 1600) – Canon PowerShot SD550 (1200 1600) – Canon PowerShot SD630 (1200 1600) – Olympus FE230/X790 (1200 1600) – Sony DSC-P10 (1200 1600) – Sony DSC-W90 (1200 1600) – Canon PowerShot A720 IS (1200 1600) – Canon PowerShot G9 (1200 1600) – Canon PowerShot S45 (1200 1600) – Fujifilm FinePix S5700 S700 (1200 1600) – Ricoh Caplio GX100 (1200 1600) – Sony DSC-T300 (1200 1600) – Canon PowerShot S410 (1200 1600) – Canon PowerShot SD700 IS (1200 1600) – Sony DSC-W55 (1200 1600) – Canon PowerShot A95 (1200 1600) – Canon PowerShot SD1100 IS (1200 1600) – Casio EX-Z57 (1200 1600) – Sony DSC-H5 (1200 1600) – Fujifilm FinePix S5600 (1200 1600) – Sony CYBERSHOT (1200 1600) – Fujifilm FinePix F100fd (1200 1600) – Fujifilm FinePix S9500 (1200 1600) – Panasonic DMC-FX35 (1200 1600) – Samsung <KENOX S1050 / Samsung S1050> (1200 1600) – Sony DSC-W150 (1200 1600) – T-Mobile Shadow T-Mobile Shadow (1200 1600) – Sony DSC-T70 (1200 1600) – CAMERA 8MP-9V9 (1200 1600) – Casio EX-Z75 (1200 1600) – Nikon E3200 (1200 1600) – Panasonic DMC-FX30 (1200 1600) – Canon PowerShot A610 (1200 1600) – Canon PowerShot G7 (1200 1600) – Canon PowerShot SD750 (1200 1600) – Olympus X100,D540Z,C310Z (1200 1600) – Sony DSC-W80 (1200 1600) – Canon PowerShot A530 (1200 1600) – Hewlett-Packard Photosmart R837 (1200 1600) – Sony DSC-W50 (1200 1600) – Canon PowerShot SD850 IS (1200 1600) – Canon PowerShot A630 (1200 1600) – Canon PowerShot S2 IS (1200 1600) – Sony DSC-P72 (1200 1600) – Canon PowerShot A710 IS (1200 1600) – Fujifilm FinePix F30 (1200 1600) – Canon PowerShot S3 IS (1200 1600) – Canon PowerShot S5 IS (1200 1600) – Sony CD MAVICA (1200 1600) – Olympus u820,S820 (1200 1600) – Canon PowerShot SD800 IS (1200 1600) – Canon PowerShot SD870 IS (1200 1600) – Canon PowerShot SD400 (1200 1600) – Nikon COOLPIX P2 (1200 1600) – Sony DSC-H2 (1200 1600) – Canon PowerShot A570 IS (1200 1600) – Canon PowerShot SD1000 (1200 1600) – Minolta DiMAGE Z1 (1200 1600) – Pentax Optio W20 (1200 1600) – Canon PowerShot SD600 (1200 1600) – Panasonic DMC-FX9 (1200 1600) – Olympus u1030SW,S1030SW (1200 1600) – Sony DSC-T9 (1200 1600)

98 Canon DIGITAL IXUS 430 (600 800) – Canon DIGITAL IXUS 75 (600 800) – Canon PowerShot S3 IS (600 800) – Fujifilm FinePix Z1 (600 800) – Olympus C120,D380 (600 800) – Panasonic DMC-FX10 (600 800) – Pentax Optio M30 (600 800) – Samsung Pro 815 (600 800) – Sony DSC-W150 (600 800) – Sony DSC-W55 (600 800) – Canon DIGITAL IXUS 65 (600 800) – Canon DIGITAL IXUS 80 IS (600 800) – Canon DIGITAL IXUS 85 IS (600 800) – Canon PowerShot G2 (600 800) – Canon PowerShot SD630 (600 800) – Olympus u850SW,S850SW (600 800) – Panasonic DMC-FX100 (600 800) – Panasonic DMC-FZ8 (600 800) – Panasonic DMC-LS80 (600 800) – Panasonic DMC-TZ3 (600 800) – Sony DSC-H3 (600 800) – Sony DSC-H5 (600 800) – Sony DSC-H9 (600 800) – Sony DSC-V3 (600 800) – Nikon COOLPIX P5000 (600 800) – Panasonic DMC-FS5 (600 800) – Casio EX-S10 (600 800) – Casio EX-Z600 (600 800) – Samsung <Samsung NV3, Samsung VLUU NV3> (600 800) – Sony CYBERSHOT (600 800) – Sony DSC-W170 (600 800) – Sony Ericsson W800i (600 800) – Canon PowerShot A630 (600 800) – Canon PowerShot SD700 IS (600 800) – Fujifilm FinePix F100fd (600 800) – Olympus u790SW,S790SW (600 800) – Sony DSC-T100 (600 800) – Canon PowerShot A590 IS (600 800) – Canon PowerShot SX100 IS (600 800) – Fujifilm FinePix F50fd (600 800) – Fujifilm FinePix S602 ZOOM (600 800) – Olympus uD800,S800 (600 800) – Canon PowerShot SX110 IS (600 800) – Panasonic DMC-FX35 (600 800) – Ricoh Caplio GX100 (600 800) – Sony DSC-P72 (600 800) – Minolta DiMAGE Z1 (600 800) – Pentax Optio WPi (600 800) – Canon PowerShot S5 IS (600 800) – Canon PowerShot SD1100 IS (600 800) – Olympus u720SW,S720SW (600 800) – Panasonic DMC-FX520 (600 800) – Canon PowerShot A430 (600 800) – Canon PowerShot SD790 IS (600 800) – Panasonic DMC-TZ5 (600 800) – Pentax Optio Z10 (600 800) – Apple iPhone (600 800) – Olympus E-410 (600 800) – Canon EOS 400D DIGITAL (600 800) – Canon PowerShot S2 IS (600 800) – Panasonic DMC-FZ10 (600 800) – Pentax Optio 50 (600 800) – Canon PowerShot SD600 (600 800) – Sony DSC-T300 (600 800) – Canon DIGITAL IXUS 970 IS (600 800) – Canon PowerShot G9 (600 800) – Fujifilm FinePix F40fd (600 800) – Nikon COOLPIX S200 (600 800) – Canon PowerShot SD400 (600 800) – Sony DSC-T7 (600 800) – Canon PowerShot A60 (600 800) – Canon PowerShot A720 IS (600 800) – Casio EX-Z1050 (600 800) – Nikon COOLPIX L3 (600 800) – Olympus C740UZ (600 800) – Fujifilm FinePix S5700 S700 (600 800) – Canon PowerShot A710 IS (600 800) – Hewlett-Packard hp photosmart 720 (600 800) – Canon PowerShot SD750 (600 800) – Fujifilm FinePix E550 (600 800) – Canon PowerShot SD850 IS (600 800) – Canon PowerShot SD870 IS (600 800) – Sony DSC-S650 (600 800) – Fujifilm FinePix F10 (600 800) – Canon PowerShot S400 (600 800) – Sony DSC-W80 (600 800) – Sony DSC-P200 (600 800) – Canon DIGITAL IXUS i7 zoom (600 800) – Panasonic DMC-LC1 (600 800) – Canon PowerShot SD800 IS (600 800) – Sony DSC-W130 (600 800) – Olympus E-300 (600 800) – Canon DIGITAL IXUS 70 (600 800) – Canon PowerShot SD1000 (600 800) – Canon PowerShot A640 (600 800) – Nikon E8700 (600 800) – Canon DIGITAL IXUS 30 (600 800) – Panasonic DMC-FZ20 (600 800)

99 Canon DIGITAL IXUS 500 (1536 2048) – Canon DIGITAL IXUS 900Ti (1536 2048) – Canon PowerShot S410 (1536 2048) – Canon PowerShot S45 (1536 2048) – Canon PowerShot SD400 (1536 2048) – Canon PowerShot SD550 (1536 2048) – Olympus E-500 (1536 2048) – Olympus FE230/X790 (1536 2048) – Panasonic DMC-FZ18 (1536 2048) – Sony DSC-H2 (1536 2048) – Sony DSC-W50 (1536 2048) – Canon DIGITAL IXUS i5 (1536 2048) – Canon PowerShot SX100 IS (1536 2048) – Olympus u710,S710 (1536 2048) – Panasonic DMC-FX30 (1536 2048) – Samsung Digimax A6 (1536 2048) – Sony DSC-F828 (1536 2048) – Sony DSC-W120 (1536 2048) – Sony DSC-W55 (1536 2048) – Canon DIGITAL IXUS 800 IS (1536 2048) – Canon PowerShot S3 IS (1536 2048) – Casio EX-Z77 (1536 2048) – Nikon COOLPIX L5 (1536 2048) – Olympus SP510UZ (1536 2048) – Panasonic DMC-FS5 (1536 2048) – Canon IXY DIGITAL 800 IS (1536 2048) – Canon PowerShot A510 (1536 2048) – Canon PowerShot A520 (1536 2048) – Casio EX-Z750 (1536 2048) – Fujifilm FinePix S5200 (1536 2048) – Panasonic DMC-TZ4 (1536 2048) – Canon PowerShot A620 (1536 2048) – Canon PowerShot SD790 IS (1536 2048) – Nikon COOLPIX L12 (1536 2048) – Sony DSC-H5 (1536 2048) – Sony DSC-P200 (1536 2048) – Canon DIGITAL IXUS 55 (1536 2048) – Canon PowerShot A460 (1536 2048) – Fujifilm FinePix S5600 (1536 2048) – Nikon E4200 (1536 2048) – Panasonic DMC-LZ7 (1536 2048) – Panasonic DMC-TZ1 (1536 2048) – Olympus X100,D540Z,C310Z (1536 2048) – Sony DSC-T33 (1536 2048) – Fujifilm FinePix S6500fd (1536 2048) – Canon PowerShot SD800 IS (1536 2048) – Canon PowerShot A560 (1536 2048) – Canon PowerShot A640 (1536 2048) – Canon PowerShot A720 IS (1536 2048) – Canon PowerShot Pro1 (1536 2048) – Olympus u720SW,S720SW (1536 2048) – Canon DIGITAL IXUS 75 (1536 2048) – Canon PowerShot G2 (1536 2048) – Canon PowerShot SD900 (1536 2048) – Casio EX-S880 (1536 2048) – Nikon COOLPIX L11 (1536 2048) – Canon PowerShot SD1100 IS (1536 2048) – Olympus FE190/X750 (1536 2048) – Canon PowerShot A710 IS (1536 2048) – Canon PowerShot SD630 (1536 2048) – Canon PowerShot SD850 IS (1536 2048) – Olympus E-300 (1536 2048) – Canon PowerShot S80 (1536 2048) – Panasonic DMC-FS3 (1536 2048) – Canon PowerShot S5 IS (1536 2048) – Sony DSC-H1 (1536 2048) – Canon PowerShot G9 (1536 2048) – Olympus C760UZ (1536 2048) – Panasonic DMC-FZ50 (1536 2048) – Canon PowerShot SD700 IS (1536 2048) – Casio EX-V8 (1536 2048) – Sony DSC-H10 (1536 2048) – Panasonic DMC-FZ7 (1536 2048) – Canon PowerShot A580 (1536 2048) – Canon PowerShot A630 (1536 2048) – Canon PowerShot S50 (1536 2048) – Sony DSC-W90 (1536 2048) – Canon PowerShot SD450 (1536 2048) – Casio EX-Z850 (1536 2048) – Fujifilm FinePix F31fd (1536 2048) – Nikon COOLPIX P80 (1536 2048) – Nikon COOLPIX P80 (1536 2048) – Nikon E4300 (1536 2048) – Fujifilm FinePix F50fd (1536 2048) – Samsung NV8 / VLUU NV8 (1536 2048) – Canon PowerShot SD600 (1536 2048) – Canon PowerShot S2 IS (1536 2048) – Canon PowerShot SD1000 (1536 2048) – Olympus E-400 (1536 2048) – Canon PowerShot SD870 IS (1536 2048) – Nikon COOLPIX S50c (1536 2048) – Panasonic DMC-TZ3 (1536 2048) – Fujifilm FinePix S9500 (1536 2048) – Nikon COOLPIX P5100 (1536 2048) – Canon PowerShot A85 (1536 2048) – Canon PowerShot SD750 (1536 2048) – Fujifilm FinePix Z20fd (1536 2048) – Canon PowerShot A530 (1536 2048) – Olympus E-510 (1536 2048) – Nikon COOLPIX L14 (1536 2048)

104 Canon DIGITAL IXUS 860 IS (600 800) – Canon PowerShot A540 (600 800) – Canon PowerShot A610 (600 800) – Canon PowerShot A80 (600 800) – Canon PowerShot G2 (600 800) – Canon PowerShot G3 (600 800) – Canon PowerShot S230 (600 800) – Canon PowerShot SD200 (600 800) – Canon PowerShot SX100 IS (600 800) – Casio EX-S600 (600 800) – Leica C-LUX 2 (600 800) – Nikon COOLPIX P5100 (600 800) – Nikon COOLPIX S200 (600 800) – Nikon COOLPIX S210 (600 800) – Nikon E4300 (600 800) – Nikon E5000 (600 800) – Olympus C8080WZ (600 800) – Olympus D595Z,C500Z (600 800) – Olympus E-510 (600 800) – Olympus FE220,X785 (600 800) – Panasonic DMC-FX33 (600 800) – Panasonic DMC-FZ7 (600 800) – Pentax Optio S4i (600 800) – Sony CYBERSHOT (600 800) – Sony DSC-P73 (600 800) – Sony DSC-W120 (600 800) – Canon PowerShot SD20 (600 800) – Canon PowerShot SD900 (600 800) – Casio EX-Z1200 (600 800) – Nikon COOLPIX S6 (600 800) – Nikon E5600 (600 800) – Sony DSC-L1 (600 800) – Sony DSC-T20 (600 800) – Sony DSC-W70 (600 800) – Canon PowerShot G10 (600 800) – Casio EX-S10 (600 800) – Fujifilm FinePix Z100fd (600 800) – Sony DSC-N1 (600 800) – Canon DIGITAL IXUS 70 (600 800) – Canon DIGITAL IXUS 850 IS (600 800) – Fujifilm FinePix F20 (600 800) – Fujifilm FinePix Z5fd (600 800) – Nikon COOLPIX P4 (600 800) – Panasonic DMC-FX07 (600 800) – Sony DSC-T30 (600 800) – Sony DSC-W90 (600 800) – Canon PowerShot A570 IS (600 800) – Canon PowerShot SD890 IS (600 800) – Fujifilm FinePix S5200 (600 800) – Nikon COOLPIX P50 (600 800) – Canon PowerShot S500 (600 800) – Canon PowerShot SD790 IS (600 800) – Canon PowerShot A520 (600 800) – Canon PowerShot SD700 IS (600 800) – Nikon COOLPIX S50 (600 800) – Fujifilm FinePix Z1 (600 800) – Canon DIGITAL IXUS 30 (600 800) – Canon DIGITAL IXUS 60 (600 800) – Canon PowerShot A640 (600 800) – Nikon COOLPIX L4 (600 800) – Sony DSC-N2 (600 800) – Canon PowerShot SD850 IS (600 800) – Casio EX-Z600 (600 800) – Fujifilm FinePix A700 (600 800) – Canon PowerShot A720 IS (600 800) – Casio EX-Z75 (600 800) – Olympus E-330 (600 800) – Canon PowerShot A590 IS (600 800) – Canon PowerShot G7 (600 800) – Canon PowerShot S5 IS (600 800) – Samsung <KENOX S1050 / Samsung S1050> (600 800) – Panasonic DMC-TZ5 (600 800) – Canon PowerShot S410 (600 800) – Ricoh R8 (600 800) – Sony DSC-W55 (600 800) – Samsung <Digimax S500 / Kenox S500 / Digimax Cyber 530> (600 800) – Canon DIGITAL IXUS 65 (600 800) – Nikon COOLPIX P2 (600 800) – Sony DSC-T10 (600 800) – Canon PowerShot SD450 (600 800) – Sony DSC-V1 (600 800) – Canon PowerShot SD870 IS (600 800) – Canon PowerShot SD550 (600 800) – Casio EX-S770 (600 800) – Fujifilm FinePix F30 (600 800) – Canon PowerShot A560 (600 800) – Panasonic DMC-FX01 (600 800) – Canon PowerShot SD400 (600 800) – Canon PowerShot G9 (600 800) – Panasonic DMC-FS3 (600 800) – Sony DSC-W7 (600 800) – Canon PowerShot SD630 (600 800) – Canon PowerShot S3 IS (600 800) – Canon PowerShot A85 (600 800) – Canon PowerShot SD1000 (600 800) – Canon PowerShot SD1100 IS (600 800) – Casio EX-Z1000 (600 800) – Canon PowerShot A530 (600 800) – Canon PowerShot SD800 IS (600 800) – Canon PowerShot SD600 (600 800) – Casio EX-Z120 (600 800) – Canon PowerShot SD750 (600 800) – Canon PowerShot A630 (600 800) – Apple iPhone (600 800)

151 Canon PowerShot A75 (600 800) – Canon PowerShot SD850 IS (600 800) – Casio EX-Z77 (600 800) – Casio EX-Z80 (600 800) – Fujifilm FinePix Z2 (600 800) – Olympus E-500 (600 800) – Olympus FE190/X750 (600 800) – Olympus u710,S710 (600 800) – Olympus u760,S760 (600 800) – Panasonic DMC-TZ1 (600 800) – Primax Gemini11 (600 800) – Samsung S85 (600 800) – Sony DSC-P10 (600 800) – Sony DSC-T10 (600 800) – Sony DSC-T1 (600 800) – Sony DSC-W110 (600 800) – Sony DSC-W35 (600 800) – Canon DIGITAL IXUS 800 IS (600 800) – Canon DIGITAL IXUS 950 IS (600 800) – Canon PowerShot A710 IS (600 800) – Canon PowerShot A95 (600 800) – Canon PowerShot SD400 (600 800) – Canon PowerShot SD900 (600 800) – Casio EX-Z60 (600 800) – Fujifilm FinePix S7000 (600 800) – MobaPhoto DSC-W70 (600 800) – Nikon COOLPIX S51 (600 800) – Nikon E7600 (600 800) – Olympus FE230/X790 (600 800) – Olympus uD800,S800 (600 800) – Samsung <KENOX S630 / Samsung S630> (600 800) – Sony DSC-H3 (600 800) – Sony DSC-T2 (600 800) – Canon PowerShot A640 (600 800) – Canon PowerShot A80 (600 800) – Casio EX-Z75 (600 800) – Fujifilm FinePix F31fd (600 800) – Olympus X600,D630,FE5500 (600 800) – Panasonic DMC-LX2 (600 800) – Pentax Optio W10 (600 800) – Sony DSC-W100 (600 800) – Sony DSC-W80 (600 800) – Canon PowerShot A460 (600 800) – Canon PowerShot A510 (600 800) – Canon PowerShot S410 (600 800) – Canon PowerShot S500 (600 800) – Canon PowerShot SD500 (600 800) – Konica Minolta DiMAGE X50 (600 800) – Nikon COOLPIX S210 (600 800) – Olympus u40D,S500,uD500 (600 800) – Panasonic DMC-FX33 (600 800) – Sony DSC-H2 (600 800) – Sony DSC-H50 (600 800) – Canon PowerShot SD870 IS (600 800) – Olympus uI030SW,S1030SW (600 800) – Samsung Digimax A5 (600 800) – Sony DSC-P150 (600 800) – LG Electronics KU990 (600 800) – Panasonic DMC-TZ2 (600 800) – Sony DSC-P52 (600 800) – Sony DSC-S500 (600 800) – Apple iPhone (600 800) – Canon DIGITAL IXUS 970 IS (600 800) – Canon PowerShot A540 (600 800) – Canon PowerShot G6 (600 800) – Nikon COOLPIX S550 (600 800) – Olympus FE220,X785 (600 800) – Pentax Optio S (600 800) – Sanyo E1 (600 800) – Sony DSC-H10 (600 800) – Canon DIGITAL IXUS 75 (600 800) – Fujifilm FinePix F40fd (600 800) – Olympus E-510 (600 800) – Olympus C700UZ (600 800) – Panasonic DMC-FX12 (600 800) – Canon PowerShot A530 (600 800) – Canon PowerShot A620 (600 800) – Canon PowerShot SD700 IS (600 800) – Canon PowerShot SX100 IS (600 800) – Sony DSC-S750 (600 800) – Canon PowerShot SD630 (600 800) – Fujifilm FinePix S9500 (600 800) – Panasonic DMC-FX01 (600 800) – Pentax Optio W30 (600 800) – Sony DSC-P100 (600 800) – Kodak EASYSHARE Z8612 IS Digital Camera (600 800) – Fujifilm FinePix F440 (600 800) – Sony DSC-W1 (600 800) – Canon PowerShot SD600 (600 800) – Fujifilm FinePix S5000 (600 800) – Nikon E2200 (600 800) – Panasonic DMC-FZ5 (600 800) – Samsung <Digimax S700 / Kenox S700 / Digimax Cyber 730> (600 800) – Canon PowerShot SD800 IS (600 800) – Samsung <Samsung D70 / D75 / S730 / S750> (600 800) – Nikon COOLPIX L11 (600 800) – Nikon COOLPIX S200 (600 800) – Canon DIGITAL IXUS 60 (600 800) – Canon IXY DIGITAL 60 (600 800) – Canon PowerShot A650 IS (600 800) – Panasonic DMC-TZ3 (600 800) – Canon PowerShot A630 (600 800) – Nikon E775 (600 800) – Sony DSC-H5 (600 800) – Canon PowerShot G7 (600 800) – Canon PowerShot G9 (600 800) – Olympus FE240/X795 (600 800) – Canon PowerShot A70 (600 800) – Sony DSC-W5 (600 800) – Canon IXY DIGITAL 910 IS (600 800) – Casio EX-Z7 (600 800) – Fujifilm FinePix V10 (600 800) – Nikon COOLPIX P5100 (600 800) – Canon PowerShot A520 (600 800) – Canon PowerShot SD1100 IS (600 800) – Fujifilm FinePix A800 (600 800) – Canon PowerShot A430 (600 800) – Canon PowerShot S2 IS (600 800) – Sony DSC-N2 (600 800) – Canon PowerShot A720 IS (600 800) – Casio EX-Z1050 (600 800) – Canon PowerShot SD450 (600 800) – Canon PowerShot A560 (600 800) – Casio EX-Z40 (600 800) – Canon PowerShot A410 (600 800) – Canon PowerShot A550 (600 800) – Canon PowerShot SD750 (600 800) – Canon PowerShot SD1000 (600 800) – Fujifilm FinePix S5700 S700 (600 800) – Fujifilm FinePix A340 (600 800) – Olympus SP560UZ (600 800) – Supra DC-6900 (600 800) – Canon PowerShot S30 (600 800) – Sony DSC-W120 (600 800) – Panasonic DMC-TZ5 (600 800) – Nikon COOLPIX P4 (600 800) – Samsung <Digimax V700 / Kenox V10 / Digimax V10 > (600 800) – Canon PowerShot A570 IS (600 800) – Nikon E5600 (600 800) – Canon PowerShot A550 (600 800) – Sony DSC-T200 (600 800) – Olympus u720SW,S720SW (600 800) – Fujifilm FinePix F10 (600 800) – Sony DSC-W50 (600 800) – Sony DSC-W55 (600 800) – Pentax Optio S7 (600 800) – Canon PowerShot S3 IS (600 800) – Konica Minolta DiMAGE Z5 (600 800) – Panasonic DMC-FZ18 (600 800) – Fujifilm FinePix Z5fd (600 800) – Nikon COOLPIX L4 (600 800) – Panasonic DMC-FZ8 (600 800)

Canon PowerShot A650 IS (960 1280) – Casio EX-S10 (960 1280) – Casio EX-V8 (960 1280) – Casio EX-Z1200 (960 1280) – Fujifilm FinePix A820 (960 1280) – Fujifilm FinePix Z5fd (960 1280) – Nikon COOLPIX L10 (960 1280) – Nikon COOLPIX L4 (960 1280) – Panasonic DMC-FX10 (960 1280) – Pentax Optio A30 (960 1280) – Sony DSC-S500 (960 1280) – Sony DSC-W170 (960 1280) – Sony DSC-W200 (960 1280) – Sony DSC-W300 (960 1280) – Sony Ericsson Z710i (960 1280) – Canon DIGITAL IXUS 750 (960 1280) – Canon IXY DIGITAL 10 (960 1280) – Canon PowerShot SD110 (960 1280) – Fujifilm FinePix A340 (960 1280) – Fujifilm FinePix F470 (960 1280) – Hewlett-Packard PhotoSmart R607 (V01.00)+ (960 1280) – Olympus FE190/X750 (960 1280) – Olympus FE250/X800 (960 1280) – Samsung Digimax A50 / KENOX Q2 (960 1280) – Sony DSC-S700 (960 1280) – Sony DSC-T70 (960 1280) – Sony DSC-W110 (960 1280) – Sony DSC-W70 (960 1280) – Canon DIGITAL IXUS 75 (960 1280) – Canon PowerShot A700 (960 1280) – Fujifilm FinePix F31fd (960 1280) – Olympus SP500UZ (960 1280) – Panasonic DMC-FX100 (960 1280) – Panasonic DMC-FZ8 (960 1280) – Sony CYBERSHOT (960 1280) – Sony DSC-H1 (960 1280) – Sony DSC-H3 (960 1280) – Sony DSC-T2 (960 1280) – Canon DIGITAL IXUS 80 IS (960 1280) – Casio EX-S770 (960 1280) – Fujifilm FinePix A610 (960 1280) – Fujifilm FinePix S5600 (960 1280) – Nikon COOLPIX L6 (960 1280) – Nikon COOLPIX S7c (960 1280) – Pentax Optio T20 (960 1280) – Pentax Optio WPi (960 1280) – Sony DSC-W1 (960 1280) – Canon PowerShot A550 (960 1280) – Canon PowerShot S500 (960 1280) – Canon PowerShot S80 (960 1280) – HITACHI HDC-761E (960 1280) – Olympus u770SW,S770SW (960 1280) – Panasonic DMC-FX35 (960 1280) – Panasonic DMC-LZ7 (960 1280) – Sony DSC-H2 (960 1280) – Sony DSC-H5 (960 1280) – Sony DSC-H9 (960 1280) – Canon PowerShot A430 (960 1280) – Canon PowerShot A510 (960 1280) – Canon PowerShot A610 (960 1280) – Canon PowerShot SD870 IS (960 1280) – Nikon COOLPIX P5100 (960 1280) – Nikon COOLPIX S550 (960 1280) – Olympus SP510UZ (960 1280) – Olympus uD800,S800 (960 1280) – Canon PowerShot A80 (960 1280) – Fujifilm FinePix F100fd (960 1280) – Fujifilm FinePix F40fd (960 1280) – Nikon E5900 (960 1280) – Panasonic DMC-FX07 (960 1280) – Panasonic DMC-LZ5 (960 1280) – Canon PowerShot A520 (960 1280) – Fujifilm FinePix S5700 S700 (960 1280) – Olympus u710,S710 (960 1280) – Sony DSC-T9 (960 1280) – Canon PowerShot A590 IS (960 1280) – Casio EX-Z850 (960 1280) – Fujifilm FinePix J10 (960 1280) – Nikon COOLPIX S3 (960 1280) – Olympus E-3 (960 1280) – Pentax OptioE20 (960 1280) – Sony DSC-T20 (960 1280) – Canon PowerShot SD700 IS (960 1280) – Panasonic DMC-TZ4 (960 1280) – Sony DSC-W5 (960 1280) – Canon EOS DIGITAL REBEL XT (960 1280) – Casio EX-Z1050 (960 1280) – Olympus FE210,X775 (960 1280) – Canon DIGITAL IXUS 55 (960 1280) – Olympus u720SW,S720SW (960 1280) – Panasonic DMC-FZ50 (960 1280) – Samsung <KENOX S1050 / Samsung S1050> (960 1280) – Sony DSC-P72 (960 1280) – Sony DSC-W50 (960 1280) – Casio EX-Z700 (960 1280) – Casio EX-Z750 (960 1280) – Sony DSC-W90 (960 1280) – Fujifilm FinePix F10 (960 1280) – Nikon S1 (960 1280) – Panasonic DMC-FZ5 (960 1280) – Canon PowerShot A560 (960 1280) – Nikon COOLPIX L11 (960 1280) – Canon DIGITAL IXUS 60 (960 1280) – Fujifilm FinePix F30 (960 1280) – Olympus FE230/X790 (960 1280) – Olympus u790SW,S790SW (960 1280) – Panasonic DMC-FZ7 (960 1280) – Sony DSC-T300 (960 1280) – Fujifilm FinePix A700 (960 1280) – Panasonic DMC-FX01 (960 1280) – Canon IXY DIGITAL 820 IS (960 1280) – Canon PowerShot A640 (960 1280) – Nikon E5600 (960 1280) – Sony DSC-W35 (960 1280) – Sony FDMAVICA (960 1280) – Canon PowerShot SD850 IS (960 1280) – Sony DSC-T100 (960 1280) – Canon IXY DIGITAL 810 IS (960 1280) – Nikon COOLPIX S51 (960 1280) – Olympus FE180/X745 (960 1280) – Panasonic DMC-TZ1 (960 1280) – Casio EX-S500 (960 1280) – Canon PowerShot A570 IS (960 1280) – Sony DSC-W120 (960 1280) – Canon PowerShot SD450 (960 1280) – Olympus u850SW,S850SW (960 1280) – Apple iPhone (960 1280) – Canon PowerShot SD300 (960 1280) – Canon PowerShot SD630 (960 1280) – Canon PowerShot SD790 IS (960 1280) – Nikon COOLPIX S500 (960 1280) – Canon PowerShot SX100 IS (960 1280) – Panasonic DMC-FZ18 (960 1280) – Canon PowerShot SD1100 IS (960 1280) – Casio EX-Z60 (960 1280) – Fujifilm FinePix F50fd (960 1280) – Nikon COOLPIX S51c (960 1280) – Panasonic DMC-L1 (960 1280) – Canon DIGITAL IXUS 70 (960 1280) – Canon PowerShot SD500 (960 1280) – Sony DSC-N2 (960 1280) – Canon PowerShot A70 (960 1280) – Canon PowerShot SD400 (960 1280) – Canon PowerShot G9 (960 1280) – Sony DSC-W80 (960 1280) – Canon PowerShot A95 (960 1280) – Sony DSC-T10 (960 1280) – Olympus C200Z,D510Z (960 1280) – Sony DSC-P200 (960 1280) – Fujifilm FinePix S5000 (960 1280) – Sony DSC-W100 (960 1280) – Olympus E-500 (960 1280) – Canon PowerShot SD750 (960 1280) – Olympus u1010,S1010 (960 1280) – Panasonic DMC-TZ5 (960 1280) – Panasonic DMC-FX36 (960 1280) – Canon PowerShot A710 IS (960 1280) – Nikon COOLPIX S50c (960 1280) – Canon PowerShot A40 (960 1280) – Canon PowerShot A540 (960 1280) – Canon PowerShot SD550 (960 1280) – Nikon COOLPIX S210 (960 1280) – Panasonic DMC-FX8 (960 1280) – Fujifilm FinePix S5200 (960 1280) – Canon PowerShot SD800 IS (960 1280) – Canon PowerShot S2 IS (960 1280) – Canon PowerShot A620 (960 1280) – Canon PowerShot S3 IS (960 1280) – Canon PowerShot A530 (960 1280) – Pentax Optio M50 (960 1280) – Canon PowerShot SD200 (960 1280) – Canon PowerShot S5 IS (960 1280) – Canon PowerShot SD1000 (960 1280) – Canon PowerShot A720 IS (960 1280) – Canon PowerShot SD600 (960 1280) – Sony DSC-W55 (960 1280) – Canon PowerShot A630 (960 1280) – Panasonic DMC-TZ3 (960 1280)